



a Wendy design **P293**

51/61 cm
20/24 ins
DK

11p



Child's Jacket and Bonnet

Knitted in Darling
Shade 800 Pure White

in

PETER PAN DARLING

(Instructions given for 51 cm. (20 inch) Chest, larger sizes given in brackets).

MATERIALS AND MEASUREMENTS

To Fit Chest Sizes.	51 20	56 22	61 24	cm. ins.
Peter Pan Darling Double Knit. JACKET BONNET	8 3	9 3	10 4	Balls Balls
Buttons. JACKET BONNET	6 1	6 1	6 1	
2 No. 8 and 2 No. 10 Aero Knitting Needles. Stitch Holder.				
Length from Top of Shoulder.	28 11	29 11½	31 12	cm. ins.
Sleeve seam.	15 6	16 6½	18 7	cm. ins.

ABBREVIATIONS

K.—Knit; P.—Purl; sts.—stitches; st.st.—stocking stitch; inc.—increase; dec.—decrease; tog.—together; rept.—repeat; alt.—alternate; beg.—beginning; cm.—centimetre; ins.—inches; g.st.—garter stitch; y.fwd.—yarn forward; y.bk.—yarn back; t.b.l.—through back of loop.

Success will be assured if you . . .

Use only the Wendy or Peter Pan yarn specified (we cannot accept responsibility for an imperfect garment if any other brand is used).

Follow our instructions exactly, make certain you have the right tension. Measure (without stretching) to see you're knitting the right number of stitches as stated. Too many?—use larger needles. Too few?—use finer needles. Once the tension is right, the size will be right.

TENSION: 8 sts. to 5 cm. (2 ins.) over pattern on No. 8 Needles.

JACKET

BACK

Using No. 10 Needles, cast on 44 (48) [52] sts.

Work 17 rows in g.st. (every row knit).

Change to No. 8 Needles and pattern.

1st Row (Wrong side facing)—K.1, * insert needle into next st. y.r.n. (yarn round finger and needle) twice, and K. Slip stitches back onto left hand needle and K. tog. t.b.l. rept. from * to last st. K.1.

2nd Row.—Knit.

These 2 rows form the pattern.

Continue in pattern until work measures 18 (18) [18] cm. 7 (7) [7] ins. from commencement finishing on a first row.

SHAPE ARMHOLES

Keeping pattern correct, cast off 5 (5) [5] sts. at beg. of next 2 rows.

K.2 tog. at each end of the needle on the next and every following alt. row until 16 (16) [16] sts. remain. Cast off.

LEFT FRONT

Using No. 10 Needles, cast on 27 (29) [31] sts.

Work 16 rows in g.st.

Next Row.—K. to last 8 sts. turn, slip these 8 sts. onto a safety pin.

Change to No. 8 Needles and pattern.

Continue in pattern as given for Back until work measures 18 (18) [18] cm. 7 (7) [7] ins. from commencement finishing on a first row.

SHAPE ARMHOLE

Cast off 5 (5) [5] sts. pattern to end.

Work 1 row.

K.2 tog. at armhole edge on next and every following alt. row until 9 (9) [9] sts. remain, finishing at neck edge.

SHAPE NECK

Next Row.—Cast off 2 (2) [2] sts. pattern to end.

Still dec. at armhole edge as before, dec. 1 st. at neck edge on the next and following alt. row. Continue to dec. at armhole edge only until 2 sts. remain. K.2 tog. Fasten off.

RIGHT FRONT

Using No. 10 Needles, cast on 27 (29) [31] sts.

Work 4 rows in g.st.

Next Row. (Buttonhole Row)—K.3, cast off 2 sts. K. to end.

Next Row.—K. to cast off sts. cast on 2 sts. K.3.

Work 10 rows in g.st.

Next Row.—K.8, slip these 8 sts. onto a safety pin, K. to end.

Change to No. 8 Needles and pattern.

Continue working to correspond with other side reversing all shapings.

SLEEVES—(Both alike)

Using No. 10 Needles, cast on 26 (28) [30] sts.

Work 25 rows in g.st. K.2 tog. at each end of the needle on the last row.

Change to No. 8 Needles and pattern.

Continue in pattern as given for Back inc. 1 st. at each end of the needle on the 3rd and every following 4th row until 32 (36) [40] sts. are on the needle. Continue without further inc. until work measures 15 (16) [18] cm. 6 (6½) [7] ins. from commencement finishing on a first row.

SHAPE TOP

Cast off 5 (5) [5] sts. at beg. of the next 2 rows.

K.2 tog. at each end of the needle on the next and every following alt. row until 4 (4) [4] sts. remain. Cast off.

LEFT FRONT BAND

With right side of work facing, slip sts. from Left Front Band onto a No. 10 Needle. Continue in g.st. until band is long enough when slightly stretched, to fit up Left Front to commencement of neck shaping. Cast off.

Mark positions for buttons on Left Front Band, the first one to correspond with buttonhole already worked, the last one 1 cm. (½ inch) from cast off edge and 4 more equally spaced between.

RIGHT FRONT BAND

With right side of work facing, slip sts. from Right Front Band onto a No. 10 Needle. Continue working to correspond with Left Front Band working buttonholes as before to correspond with positions marked for Buttons.

COLLAR

Using No. 10 Needles, cast on 46 (48) [50] sts.

Work 26 rows in g.st.

Cast off loosely.

BONNET

Using No. 10 Needles, cast on 59 (65) [71] sts.

Work 15 rows in g.st.

Change to No. 8 Needles and pattern. Continue in pattern as given for Back of Jacket until work measures 10 (11) [12] cm. 4 (4½) [4¾] ins. from commencement finishing on a wrong side row.

SHAPE BACK

Keeping the pattern correct, cast off 10 (11) [12] sts. at beg. of the next 4 rows. K.2 tog. at each end of the needle on the 4th and every following 6th row until 13 (15) [17] sts. remain.

Continue without further dec. until Back measures 10 (11) [12] cm. 4 (4½) [4¾] ins. finishing on a wrong side row.

Slip sts. onto a st. holder.

PRESSING

It is important to follow these instructions when making up the garment.

With wrong side of work facing, pin out all pieces to measurements given. Using a warm iron and dry cloth, press carefully.

MAKING UP

JACKET

Pin sleeves into position, sew in by backstitching.

Join side and sleeve seams by backstitching, omitting g.st, Join g.st. by top sewing.

Pin Front bands into position sew on by top sewing.

Pin Collar into position round neck edge, the right side of collar to inside of garment the ends of collar to centre of front bands, sew on by top sewing.

Fold collar onto right side.

Sew on buttons to correspond with buttonholes

Buttonhole stitch buttonholes.

Press seams lightly.

BONNET

Join seams by top sewing.

Using No. 10 Needles, cast on 8 sts. With right side of work facing, pick up and K.17 (18) [19] sts. along side edge, K. sts. from stitch holder, pick up and K.17 (18) [19] sts. along side edge, cast on 8 sts.

Knit 3 rows.

Next Row.—K. to the last 5 sts. cast off 2 sts. K. to end.

Next Row.—K.3, cast on 2 sts. K. to end.

Knit 3 more rows.

Cast off loosely in g.st.

Sew on button to correspond with buttonhole.

Buttonhole stitch buttonhole.

Press seams lightly.

A FINAL WORD

You have taken a lot of care in knitting this Peter Pan Design. Your garment deserves equal care when washing. By following these instructions, you will find that the life shape and softness of your garment will be preserved.

- (1) **NEVER USE HOT WATER**
- (2) **Washing.** Place your garment in a well-dissolved solution of **Soap Flakes** and **WARM WATER**. Work the garment gently with the hands for approximately two minutes **NEVER RUB** the garment and do **NOT** leave it to soak
- (3) **Rinsing.** **EVERY TRACE OF SOAP MUST BE REMOVED**. Rinse in three changes of clean warm water, squeezing gently, but **NEVER** wring the garment.
- (4) **Removing Water.** Place the garment between dry towels and squeeze without twisting
- (5) **Drying.** Immediately spread the garment out to its original shape and size and **DRY FLAT** on a clean towel. **SLOWLY**, and in a warm place **NEVER** hang up your garment to dry

MACHINE WASHING

Instructions on ball band



Our Knitting Bureau will gladly give you any assistance or advice on Wendy Designs if queries are accompanied by a Wendy or Peter Pan Ball Band and a stamped addressed envelope

CARTER & PARKER LTD, GUISELEY, YORKS.

Prices apply only in Great Britain and Northern Ireland

PRINTED IN ENGLAND