

PRICE
CODE **C** **3067**
51-66 cm
20-26 in
★ ★ ★



ZIG ZAG LACE CARDIGAN

To fit chest

51	56	61	66	cm
20	22	24	26	in (approx)

Actual size

57	62	66	73	cm
22½	24½	26	28½	in (approx)

Finished length

30	35	38	42	cm
12	14	15	16½	in (approx)

Patons Fairytale Misty Brushed DK

4	4	5	5	40 gram balls
---	---	---	---	---------------

Patons Fairytale DK

3	4	4	5	50 gram balls
---	---	---	---	---------------


or 100 gram "Magic Value" balls

2	2	2	3	
---	---	---	---	--

★★★ For knitters with some experience

Caution

It is essential to work to the stated tension, and we cannot accept responsibility for the finished product if any yarn other than the specified yarns is used.



Quantities of yarn are approximate as they are based on average requirements.

Although every effort is made to ensure that the colours on this leaflet are true representations of their respective yarns, they may not always exactly match due to technical restrictions of printing processes.

We recommend Milward or Susan Bates knitting needles.

Pair each Nos 3¼ mm and 4 mm needles.

5 [5, 6, 6] buttons.

Tension

On No 4 mm needles, 20 sts and 33 rows to 10 cm (patt), 22 sts and 30 rows to 10 cm (stocking st).

It is important to check your tension before starting your garment. If there are too many stitches to 10 cm, your tension is tight and you should change to a larger size needle. If there are too few, your tension is loose and you should change to a smaller size needle.

Abbreviations

K=knit; **P**=purl; **st**=stitch; **tog**=together; **tbl**=through back of loops; **inc**=increase by working into front and back of stitch; **dec**=decrease by working 2 stitches together; **beg**=beginning; **alt**=alternate; **rep**=repeat; **cm**=centimetres; **in**=inches; **mm**=millimetres; **sL1K**=slip 1 knit-ways; **yfwd**=yarn forward; **yrn**=yarn round needle; **psso**=pass slip

stitch over; **patt**=pattern; **0**=no st or time to be worked in this size.

M1=make a stitch by picking up horizontal loop lying before next stitch and working into back of it.

NB. DO NOT "MAKE 1" by knitting into the front and back of a stitch.

Instructions are given for the first size, with larger size(s) given in square brackets []. Where only one figure is given this applies to both (all) sizes.

BACK

With No 3¼ mm needles, cast on 53 [59, 65, 71] sts and work in rib as follows:

1st row—(Right side), K1, * P1, K1; rep from * to end.

2nd row—P1, * K1, P1; rep from * to end.

Rep these 2 rows for 5 [5, 6, 6] cm, ending with a 1st row.

Next row—In rib inc 3 [3, 1, 1] sts evenly (56 [62, 66, 72] sts).

Change to No 4 mm needles and work in **patt** as follows:

1st row—(Right side), K1 [0, 2, 1], * K2tog, yfwd, K2; rep from * to last 3 [2, 0, 3] sts, (K2tog, yfwd) 1 [0, 0, 1] time, K1 [2, 0, 1].

2nd row—P0 [1, 1, 0], (yrn, P2tog) 0 [1, 0, 0] time, * P2, yrn, P2tog; rep from * to last 0 [3, 1, 0] sts, P0 [3, 1, 0].

3rd row—K3 [2, 0, 3], * K2tog, yfwd, K2; rep from * to last 1 [0, 2, 1] sts, K1 [0, 2, 1].

4th row—P2 [1, 1, 2], (yrn, P2tog) 0 [0, 1, 0] time, * P2, yrn, P2tog; rep from * to last 2 [1, 3, 2] sts, P2 [1, 3, 2].

5th row—K2 [1, 3, 2], * yfwd, sL1K, K1, psso, K2; rep from * to last 2 [1, 3, 2] sts, (yfwd, sL1K, K1, psso) 1 [0, 1, 1] time, K0 [1, 1, 0].

6th row—P1 [0, 0, 1], (P2togtbl, yrn) 0 [0, 1, 0] time, * P2, P2togtbl, yrn; rep from * to last 3 [2, 4, 3] sts, P3 [2, 4, 3].

7th row—K4 [3, 1, 4], * yfwd, sL1K, K1, psso, K2; rep from * to last 0 [3, 1, 0] sts, (yfwd, sL1K, K1, psso) 0 [1, 0, 0] time, K0 [1, 1, 0].

8th row—P1 [0, 0, 1], (P2togtbl, yrn) 1 [1, 0, 1] time, * P2, P2togtbl, yrn; rep from * to last 1 [4, 2, 1] sts, P1 [4, 2, 1].

These 8 rows form patt.

Continue in patt until Back measures 30 [35, 38, 42] cm (or adjust to suit), ending with right side facing for next row.

Shape shoulders by casting off 6 [7, 7, 8] sts at beg of next 4 rows, then 6 [7, 8, 8] sts at beg of following 2 rows.

Leave remaining 20 [20, 22, 24] sts on a spare needle.

LEFT FRONT

** With No 3¼ mm needles, cast on 23 [27, 29, 31] sts and work in rib as on Back for 5 [5, 6, 6] cm, ending with a 1st row.

Next row—In rib, inc 2 [1, 1, 2] sts evenly (25 [28, 30, 33] sts).

Change to No 4 mm needles and work in **patt** as follows: **

1st row—(Right side), K1 [0, 2, 1], * K2tog, yfwd, K2; rep from * to end.

2nd row—P1, * P2, yrn, P2tog; rep from * to last 0 [3, 1, 0] sts, P0 [3, 1, 0].

3rd row—K3 [2, 0, 3], * K2tog, yfwd, K2; rep from * to last 2 sts, K2.

4th row—P1, yrn, P2tog, * P2, yrn, P2tog; rep from * to last 2 [1, 3, 2] sts, P2 [1, 3, 2].

5th row—K2 [1, 3, 2], * yfwd, sL1K, K1, psso, K2; rep from * to last 3 sts, yfwd, sL1K, K1, psso, K1.

6th row—P2togtbl, yrn, * P2, P2togtbl, yrn; rep from * to last 3 [2, 4, 3] sts, P3 [2, 4, 3].

7th row—K4 [3, 1, 4], * yfwd, sL1K, K1, psso, K2; rep from * to last st, K1.

8th row—* P2, P2togtbl, yrn; rep from * to last 1 [4, 2, 1] sts, P1 [4, 2, 1].

These 8 rows form patt.

Continue in patt until 14 [14, 14, 16] rows less than on Back have been worked before start of shoulder shaping, thus ending with right side facing for next row.

Shape neck as follows:

Next row—Patt 23 [26, 27, 29], turn and leave remaining 2 [2, 3, 4] sts on a safety-pin.

Dec 1 st at neck edge on next 2 rows, then on following 3 alt rows (18 [21, 22, 24] sts).

Work 5 [5, 5, 7] rows, thus ending with right side facing for next row.

Shape shoulders by casting off 6 [7, 7, 8] sts at beg of next and following alt row. Work 1 row.

Cast off remaining 6 [7, 8, 8] sts.

RIGHT FRONT

Work as for Left Front from ** to **.

1st row—(Right side), K2, * K2tog, yfwd, K2; rep from * to last 3 [2, 0, 3] sts, (K2tog, yfwd) 1 [0, 0, 1] time, K1 [2, 0, 1].

2nd row—P0 [1, 1, 0], (yrn, P2tog) 0 [1, 0, 0] time, * P2, yrn, P2tog; rep from * to last st, P1.

3rd row—* K2tog, yfwd, K2; rep from * to last 1 [0, 2, 1] sts, K1 [0, 2, 1].

4th row—P2 [1, 1, 2], (yrn, P2tog) 0 [0, 1, 0] time, * P2, yrn, P2tog; rep from * to last 3 sts, P3.

5th row—K3, * yfwd, sL1K, K1, psso, K2; rep from * to last 2 [1, 3, 2] sts, (yfwd, sL1K, K1, psso) 1 [0, 1, 1] time, K0 [1, 1, 0].

6th row—P1 [0, 0, 1], (P2togtbl, yrn) 0 [0, 1, 0] time, * P2, P2togtbl, yrn; rep from * to last 4 sts, P4.

7th row—K1, * yfwd, sL1K, K1, psso, K2; rep from * to last 0 [3, 1, 0] sts, (yfwd, sL1K, K1, psso) 0 [1, 0, 0] time, K0 [1, 1, 0].

8th row—P1 [0, 0, 1], (P2togtbl, yrn) 1 [1, 0, 1] time, * P2, P2togtbl, yrn; rep from * to last 2 sts, P2.

These 8 rows form patt.

Continue in patt and work to match Left Front, reversing shapings, **noting** that an extra row will have to be worked before start of shoulder shaping.

SLEEVES

With No 3¼ mm needles, cast on 31 [33, 35, 37] sts and work in rib as on

Back for 3 [3, 4, 4] cm, ending with a 1st row.

Next row—Rib 3 [4, 3, 4], * M1, rib 6 [6, 7, 7]; rep from * to last 4 [5, 4, 5] sts, M1, rib to end (36 [38, 40, 42] sts).

Change to No 4 mm needles and work in **patt** as follows:

1st row—(Right side), K3 [0, 1, 2], * K2tog, yfwd, K2; rep from * to last 1 [2, 3, 0] sts, (K2tog, yfwd) 0 [0, 1, 0] time, K1 [2, 1, 0].

2nd row—P2 [1, 0, 1], (yrn, P2tog) 0 [1, 0, 0] time, * P2, yrn, P2tog; rep from * to last 2 [3, 0, 1] sts, P2 [3, 0, 1].

3rd row—K1 [2, 3, 0], * K2tog, yfwd, K2; rep from * to last 3 [0, 1, 2] sts, (K2tog, yfwd) 1 [0, 0, 0] time, K1 [0, 1, 2].

4th row—P0 [1, 2, 1], (yrn, P2tog) 0 [0, 0, 1] time, * P2, yrn, P2tog; rep from * to last 0 [1, 2, 3] sts, P0 [1, 2, 3].

5th row—K4 [1, 2, 3], * yfwd, sL1K, K1, psso, K2; rep from * to last 0 [1, 2, 3] sts, (yfwd, sL1K, K1, psso) 0 [0, 1, 1] time, K0 [1, 0, 1].

6th row—P1 [0, 1, 0], (P2togtbl, yrn) 1 [0, 0, 1] time, * P2, P2togtbl, yrn; rep from * to last 1 [2, 3, 4] sts, P1 [2, 3, 4].

7th row—K2 [3, 4, 1], * yfwd, sL1K, K1, psso, K2; rep from * to last 2 [3, 0, 1] sts, (yfwd, sL1K, K1, psso) 1 [1, 0, 0] time, K0 [1, 0, 1].

8th row—P1 [0, 1, 0], (P2togtbl, yrn) 0 [1, 1, 0] time, * P2, P2togtbl, yrn; rep from * to last 3 [4, 1, 2] sts, P3 [4, 1, 2].

These 8 rows form patt.

Continue in patt, shaping sides by inc 1 st at each end of 11th [9th, 9th, 9th] row (from beg of patt) and every following 12th [10th, 10th, 10th] row until there are 46 [44, 48, 48] sts, taking inc sts into patt.

2nd, 3rd and 4th sizes: Inc 1 st at each end of every following 12th row until there are [50, 54, 58] sts, taking inc sts into patt.

All sizes: Work 11 rows.

Cast off **loosely**.

MAKE UP AND BORDERS

Do not press.

Join shoulder seams.

Place centre of cast-off edge of sleeves to shoulder seams and sew Sleeves in position to Back and Fronts.

Join side and sleeve seams.

Neck Border: With right side facing and No 3¼ mm needles, starting at right front K2 [2, 3, 4] from safety-pin, **knit up** 13 [13, 13, 15] sts up right side of neck, K20 [20, 22, 24] from back inc 1 st at centre, **knit up** 13 [13, 13, 15] sts down left side of neck, then K2 [2, 3, 4] from safety-pin (51 [51, 55, 63] sts).

Starting with a 2nd row, work in rib as on Back for 5 cm.

Using a No 4 mm needle, cast off loosely in rib.

Fold Neck Border in half to wrong side and slip-hem loosely in position.

HANDY HINTS

When marking position of buttons on Button Border with pins, mark first and last buttons as specified, then count the number of rows in between. Divide those rows as evenly as possible for the remaining buttons required and place pins accordingly, then make sure that the same number of rows are worked on the Buttonhole Border between each buttonhole placing.

Button Border: With No 3¼ mm needles, cast on 9 sts and work in rib as follows:

1st row—(Right side), K2, (P1, K1) 3 times, K1.

2nd row—K1, (P1, K1) 4 times.

Rep these 2 rows until Border, when slightly stretched, fits up Left Front to top of Neck Border, sewing in position as you go along.

Cast off evenly in rib.

Mark position of 5 [5, 6, 6] buttons on Button Border with pins to ensure that even spacing, first to come 1 cm up from lower edge, last to come 1 cm down from top of Neck Border and remainder spaced evenly between (see Handy Hints).

Buttonhole Border: Work as for Button Border with the addition of 5 [5, 6, 6] buttonholes to correspond with pins placed on Button Border.

To make a buttonhole: Rib 4, yfwd, K2tog, rib to end.

Sew on buttons.

Do not dry handknits in harsh sunlight as fading or yellowing may occur.

WASHING AND CARING FOR PATONS YARNS

Hand washing is always best. For yarns made mainly of wool use warm water, a warm rinse, squeeze out between towels or spin-dry (normal cycle), then dry flat after easing into shape. Do not dry in direct heat (radiators or fires). Do not dry white handknits in direct sunlight. For yarns made mainly of acrylics it is important that you rinse in cold water and if you spin-dry use the short cycle.

A great many people now use washing machines. The ball band will show whether the yarn you have chosen is suitable for machine-washing: if it is, follow these four "golden rules".

1. Make sure the garment is knitted correctly according to the Patons pattern, on the correct needles to the correct tension.
2. Don't have the water hotter than the recommended temperature.
3. Use the machine on a gentle cycle.
4. Don't leave the garment in the machine too long.

The wrappers on all Patons yarns show the appropriate International Textile Care Labelling Code symbols for the yarn. Examples are shown here. The latest automatic machines have these International Care Symbols, and provided your machine is not connected to the domestic hot water supply (when you need to be careful about the heat) all you have to

do is match the programme to our symbols. Older types of machine will not have these controls and it may be more difficult to ensure the correct combination of temperature, agitation and time.

If you are in any way unsure about the application of the symbols to your machine it is safest to hand-wash.

WASH SYMBOLS

	Machine	Hand wash
	Warm (40°C)	Warm (40°C)
	Maximum wash	
	Normal rinse and spin	
	Do not rub or hand-wring	Dry flat
	Machine	Hand wash
	Warm (40°C)	Warm (40°C)
	Minimum wash	
	Cold rinse	Short spin Do not wring
	Machine	Hand wash
	Warm (40°C)	Warm (40°C)
	Minimum wash	Do not rub
	Spin	Do not rub or hand-wring
	Dry flat	

	Hand wash only	
	Warm (40°C)	
	Warm rinse	Do not rub or hand-wring
	Dry flat	
BLEACH SYMBOLS		Household bleach can be used
		Do not bleach
IRONING SYMBOLS		Cool Iron (120°C)
		Warm Iron (160°C)
		Do not Iron
DRY CLEANING SYMBOLS		Dry cleanable in all solvents
		Dry cleanable in certain solvents
		Consult cleaner
		Do not dry clean