



P141

1/-



a Wendy design

Sweater, Romper and Cap

in

Peter Pan

as listed below under "Materials Required"

THREE IMPORTANT POINTS

- 1** Be certain to buy sufficient of the correct WENDY PETER PAN to complete the garment. You will then avoid any difficulty in obtaining an exact match.
- 2** The instructions for all PETER PAN designs are written, checked and re-checked by a highly qualified staff. Please follow them exactly and the success of your garment is assured.
- 3** *The key to successful crochet is correct tension.* The instructions for all crochet garments are based on pre-determined tension. Before attempting to follow any instructions in this leaflet, make quite sure that *you can achieve the stipulated tension.*

The hook has been selected to give the required tension, but some workers may experience difficulty in obtaining *the correct number of stitches to the inch.* If you find that you obtain more stitches to the inch with the recommended hook, then use a larger size. If, however, you obtain less stitches to the inch with the recommended hook, then use a finer size.

Whatever size of hook you choose, *make certain that you obtain the tension stated for this garment.*

(Instructions given for 18 inch chest, 20 inch size given in brackets).

MATERIALS REQUIRED

SWEATER	—	5 (6) ozs.	}	Peter Pan Baby Courtelle Double Knit
ROMPER	—	4 (5) ozs.		or
CAP	—	2 (2) ozs.		Peter Pan Baby Bri Nylon Double Knit
1 oz. less required for complete set.				
No. 7 Aero Crochet hook—Bri-Nylon.				
No. 8 Aero Crochet hook—Courtelle.				
6 Buttons—Sweater.				
2 Buttons—Romper.				

MEASUREMENTS

SWEATER	—	Length from top of shoulder— $9\frac{1}{2}$ ($10\frac{1}{2}$) ins.
		To fit —18 (20) inch chest.
		Sleeve seam—5 (6) ins.
ROMPER	—	Side length to armhole— $6\frac{3}{4}$ ($7\frac{3}{4}$) ins.
CAP	—	Round Face—12 (13) ins.

ABBREVIATIONS

Ch.—chain.	d.c.—double crochet.	sts.—stitches.	sl. st.—slip stitch.
ins.—inches.	inc.—increase.	dec.—decrease.	w.o.h.—wool over hook.

SPECIAL NOTE ON COURTELLE TENSION

When working in Courtelle it is most important to crochet a tension square. Using one size smaller crochet hook, No. 8 in place of No. 7. If correct tension is not achieved adjust your crochet hook as in paragraph 3 of Important Points.

THE TENSION FOR THIS GARMENT IS:

$4\frac{1}{2}$ sts. to 1 inch, using No. 7 Crochet hook, No. 8 Courtelle.

Story of "Peter Pan" by permission of The Hospital for Sick Children, Great Ormond Street, London, W.1, who receive part of proceeds from this leaflet.

SWEATER

BACK

Using No. 7 crochet hook, No. 8 in place of No. 7 to be used throughout this garment if working in Courteille, make 45 (49) ch.

Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—44 (48) d.c., turn with 1 ch.

COMMENCE PATTERN

1st Row.—1 d.c. into first st. * insert hook into last st., worked into, w.o.h. and draw loop through, hook into next st., w.o.h. and draw loop through, w.o.h. and draw through 3 loops on hook, rept. from * to end, 1 d.c. into 1 ch. turn of previous row, turn with 1 ch.

This row forms the pattern.

Continue in pattern until work measures $5\frac{1}{2}$ (6) ins. from commencement.

SHAPE ARMHOLES

Next Row.—Sl. st. over 3 sts., work to within 3 sts. of end, turn.

Next Row.—Sl. st. over 1 st., work to within 1 st. of end, turn.

Rept. the last row once more.—34 (38) sts.

Continue without further dec. until work measures $9\frac{1}{4}$ (10 $\frac{1}{4}$) ins. from commencement.

SHAPE SHOULDER

Next Row.—Sl. st. over 5 (6) sts., work to within 5 (6) sts. of end, turn.

Rept. the last row once more. Fasten off.

LEFT FRONT

Using No. 7 crochet hook, make 20 (22) ch.

Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—19 (21) d.c.

Continue in pattern as given for Back until work measures $5\frac{1}{2}$ (6) ins. from commencement.

SHAPE ARMHOLE

Next Row.—Sl. st. over 3 sts., work to end.

Next Row.—Work to last st., turn.

Next Row.—Sl. st. over 1 st., work to end.—14 (16) sts.

Continue without further dec. until work measures $8\frac{1}{2}$ (9 $\frac{1}{4}$) ins. from commencement, finishing at armhole edge.

SHAPE NECK

Next Row.—Pattern across 12 (14) sts., turn.

Next Row.—Sl. st. over 1 st., work to end.

Next Row.—Pattern across 10 (12) sts., turn.

Continue without further dec. until work measures $9\frac{1}{4}$ (10 $\frac{1}{4}$) ins. from commencement, finishing at armhole edge.

SHAPE SHOULDER

Next Row.—Sl. st. over 5 (6) sts., work to end.

Fasten off.

Mark positions for buttons, the first one 2 rows from lower edge, the last one 2 rows from shoulder shaping and 4 more equally spaced between.

RIGHT FRONT

Using No. 7 crochet hook, make 34 (36) ch.

Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—33 (35) d.c.

Continue in pattern as given for Back, work 1 row.

Next Row.—(Buttonhole Row)—Pattern 2 sts., 1 ch., miss 1 st., pattern to end.

Continue in pattern, working buttonholes as before to correspond with positions marked for buttons, until work measures $5\frac{1}{2}$ (6) ins. from commencement, finishing at side edge.

SHAPE ARMHOLE

Next Row.—Sl. st. over 3 sts., work to end.

Next Row.—Work to within 1 st. of end, turn.

Next Row.—Sl. st. over 1 st., work to end.—28 (30) sts.

Continue without further dec. working buttonholes as before until work measures $8\frac{1}{2}$ (9 $\frac{1}{4}$) ins. from commencement, finishing at front edge.

SHAPE NECK

Next Row.—Pattern over 6 sts., turn.

Next Row.—Sl. st. over 1 st., work to end.

Next Row.—Pattern over 4 sts. turn.

Continue working on these 4 sts. until work measures $9\frac{1}{4}$ (10 $\frac{1}{4}$) ins. from commencement.

Fasten off.

Leave 10 sts. free at centre for neck.

Rejoin yarn and work across remaining 12 (14) sts.

Dec. 1 st. at neck edge on the next 2 rows.

Continue without further dec. until work measures $9\frac{1}{4}$ (10 $\frac{1}{4}$) ins. from commencement, finishing at armhole edge.

SHAPE SHOULDER

Next Row.—Sl. st. over 5 (6) sts., work to end.

Fasten off.

SLEEVES—(Both alike)

Using No. 7 crochet hook, make 24 (26) ch.

Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—23 (25) d.c.

Continue in pattern as given for Back, working all inc. sts. into pattern, inc. 1 st. at each end of the 10th (8th) and every following 10th (8th) rows until there are 27 (31) sts. on the row.

Continue without further inc. until work measures 5 (6) ins. from commencement.

SHAPETOP

Next Row.—Sl. st. over 3 sts., work to within 3 sts. of end, turn.

Next Row.—Sl. st. over 1 st., work to within 1 st. of end, turn.

Rept. the last row 3 (4) times more.

Next Row.—Sl. st. over 2 sts., work to within 2 sts. of end, turn.

Rept. the last row once more.

Fasten off.

ROMPER

BACK—(Commence at crutch)

Using No. 7 crochet hook, make 12 (14) ch.

Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—11 (13) d.c.

Continue in pattern as given for Back of Sweater, inc. 1 st. at each end of every row until there are 35 (39) sts. on the row.

Work 1 row.

Inc. 4 sts. at each end of the next row.—43 (47) sts.

Continue in pattern dec. 1 st. at each end of the 12th and following 12th row.

Continue without further dec. until side edge measures $6\frac{1}{2}$ (7 $\frac{1}{2}$) ins.

SHAPE ARMHOLES

Next Row.—Sl. st. over 4 sts. work to within 4 sts. of end, turn.

Continue without further dec. until armhole measures 3 (3 $\frac{1}{2}$) ins. measured straight.

Next Row.—Pattern across 9 (10) sts. turn.

Continue in pattern on these 9 (10) sts. for strap.

Work 3 (3 $\frac{1}{2}$) ins.

Next Row.—(Buttonhole Row)—Pattern 4 sts., 1 (2) ch., miss 1 (2) sts., work to end.
Work 1 row, working 1 (2) sts. into the 1 (2) ch.
Fasten off.
Leave 15 (17) sts. free at centre for neck.
Rejoin yarn to remaining 9 (10) sts. and work to correspond with other side.

FRONT

Using No. 7 crochet hook, make 12 (14) ch.
Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—11 (13) d.c.
Continue in pattern as given for Back of Sweater.
Work 8 (10) rows.
Inc. 1 st. at each end of every row until there are 27 (29) sts. on the row.
Work 1 row.
Make 9 (11) ch. turn.
Work into 2nd ch. from hook, pattern to end.
Make 9 (11) ch. turn.
Work into 2nd ch. from hook, pattern to end.—43 (47) sts.
Continue in pattern dec. 1 st. at each end of the 12th and following 12th row.
Continue without further dec. until side edge measures $6\frac{1}{2}$ ($7\frac{1}{2}$) ins.

SHAPE ARMHOLES

Next Row.—Sl. st. over 4 sts., work to within 4 sts. of end, turn.
Continue without further dec. until armhole measures 2 $\frac{1}{2}$ (3) ins. measured straight.
Fasten off.

CAP

Using No. 7 crochet hook, make 50 (54) ch.
Work 1 d.c. into 2nd ch. from hook, 1 d.c. into each ch. to end.—49 (53) d.c.
Continue in pattern as given for Back of Sweater until work measures 4 ($4\frac{1}{2}$) ins. from commencement.
Fasten off.
Break off yarn.
Leave 17 (18) sts. free at each end of the row, rejoin yarn to remaining 15 (17) sts. for Back section.
Continue in pattern, dec. 1 st. at each end of the 4th and every following 6th row until 9 (11) sts. remain.
Continue without further dec. until back section measures 4 ($4\frac{1}{4}$) ins.
Fasten off.

PRESSING

It is **important** to follow these instructions when making up the garment.

PETER PAN COURTELLE ONLY

Work over the right side of each piece of the garment with a cool iron. Taking a small area at a time, stretch your crochet lengthways and sideways (pull hard) let it relax, then pat over with the iron using no pressure. This evens out the crochet and sets it.

PETER PAN BRINYLYN

With wrong side of work facing, pin out all pieces to measurements given. Using a warm iron and dry cloth press carefully.

MAKING UP

SWEATER

Join shoulder seams by back stitching.
Join side and sleeve seams by top sewing.

Pin sleeves into position, sew in by back stitching.
With right side of work facing, work 1 row d.c. evenly up right front, round neck edge, down left front and round lower edge. Fasten off.
Work 1 row d.c. round lower edge of sleeves.
Sew on buttons to correspond with buttonholes.
Buttonhole stitch buttonholes.

ROMPER

Join crutch and side seams by top sewing.
Work 1 row d.c. evenly round legs, armholes, neck and straps.
Sew on buttons to top edge of front.
Buttonhole stitch buttonholes.

CAP

Join back seams by top sewing.
With right side of work facing, rejoin yarn, work 2 rows d.c. evenly round neck edge.
Next Row.—2 d.c. * 1 ch., miss 1 d.c., 2 d.c., rept. from * to end.
Work 1 row d.c., working 1 d.c. into 1 ch. space.
Next Row.—d.c. round neck edge and continue round front edge.
Fasten off.
Make cord and thread through holes at neck.
Press all seams and borders lightly.

A FINAL WORD

You have taken a lot of care in working this Peter Pan Design. Your garment deserves equal care when washing. By following these instructions, you will find that the life, shape and softness of your garment will be preserved.

- (1) **NEVER USE HOT WATER.**
- (2) **Washing.** Place your garment in a well-dissolved solution of Soap Flakes and WARM WATER. Work the garment gently with the hands for approximately two minutes. **NEVER RUB** the garment and do NOT leave it to soak.
- (3) **Rinsing.** EVERY TRACE OF SOAP MUST BE REMOVED. Rinse in three changes of clean warm water, squeezing gently but **NEVER wring** the garment.
- (4) **Removing Water.** Place the garment between dry towels and squeeze without twisting.
- (5) **Drying.** Immediately spread the garment out to its original shape and size and **DRY FLAT** on a clean towel, **SLOWLY**, and in a warm place. **NEVER** hang up your garment to dry.

WASHING



SO EASY TO WASH AND CARE FOR

Treat your own make of crochet in Courtelle just as you would bought ones. That is, **WASH** by hand, as soon as they get slightly dirty. Use soapless detergent or soap flakes or powder dissolved in water comfortably hot to the hand. **RINSE** thoroughly. Squeeze lightly or roll in towel. Do *not* put through wringer. **DRY** flat.

Do *not* press with a damp cloth, instead, work over the right side of each garment piece with a **COOL** iron (set at Rayon temperature). Taking a small area at a time, stretch your crochet lengthways and sideways (pull hard), let it relax, then pat over it with the iron, using no pressure. This evens out the crochet and sets it.

Our Knitting Bureau will gladly give you any assistance or advice on Wendy Designs if you write to
CARTER & PARKER LTD., GUISELEY, YORKS.

Prices apply only in Great Britain and Northern Ireland