



a Wendy design
18/20" CHEST
4 PLYS

P200

5p
1/-



Angel Top and Tights in PETER PAN

Knitted in 4 ply Courtelle

Shade 50I Rosebud

504 Pure White

(Instructions given for 18 inch Chest, larger size given in brackets).

MATERIALS REQUIRED

ANGEL TOP	—	4 (4) Balls	}	PETER PAN BABY COURTELLE 4 PLY.
TIGHTS	—	5 (6) Balls		
or				
ANGEL TOP	—	6 (6) 20 gram Balls	}	PETER PAN BABY BRI NYLON 4 PLY or
TIGHTS	—	8 (9) 20 gram Balls		
2 No. 11 and 2 No. 13 Aero Knitting Needles.				
Stitch holder.				
5 Buttons.				
Elastic.				

MEASUREMENTS

ANGEL TOP	—	Length from back of neck – $9\frac{1}{2}$ (11) ins. To fit – 18 (20) inch Chest. Sleeve seam – 5 (6) ins.
TIGHTS	—	Side length to ankle – $14\frac{1}{2}$ ($16\frac{1}{2}$) ins.

ABBREVIATIONS

K.—Knit.	st.st.—stocking stitch.	tog.—together.	inc.—increase.
P.—Purl.	sl.1.—slip one.	rept.—repeat.	dec.—decrease.
sts.—stitches.	p.s.s.o.—pass slipped stitch over.	beg.—beginning.	y.fwd.—yarn forward.
ins.—inches.			
0.—No sts. or rows to be worked in that particular size.			

SUCCESS WILL BE ASSURED IF YOU

follow our instructions exactly and your Wendy or Peter Pan garment will knit up successfully. Make certain you have the right tension. Measure (without stretching) to see you're knitting the right number of stitches to an inch. Too many? – use larger needles. Too few? – use finer needles. Once the tension is right, the size will be right.

Story of "Peter Pan" by permission of THE HOSPITAL FOR SICK CHILDREN, Great Ormond Street, London, W.1, who receive part of proceeds from this Leaflet.

ANGEL TOP

THE TENSION FOR THIS GARMENT IS:- 7 sts. to 1 inch over pattern on No. 11 needles.

COMMENCE AT LOWER EDGE

Using No. 13 needles, cast on 163 (183) sts.

Knit 8 rows.

Change to No. 11 needles.

COMMENCE PATTERN

1st Row.—K.2. * y.fwd., sl.1, K.1, p.s.s.o., K.5, K.2 tog., y.fwd., K.1, rept. from * to last st., K.1.

2nd and Alt. Rows.—Purl.

3rd Row.—K.2. * K.1, y.fwd., sl.1, K.1, p.s.s.o., K.3, K.2 tog., y.fwd., K.2, rept. from * to last st., K.1.

5th Row.—K.2. * K.2, y.fwd., sl.1, K.1, p.s.s.o., K.1, K.2 tog., y.fwd., K.3, rept. from * to last st., K.1.

7th Row.—K.2. * K.1, y.fwd., sl.1, K.1, p.s.s.o., y.fwd., sl.1, K.2 tog., p.s.s.o., y.fwd., K.2 tog., y.fwd., K.2, rept. from * to last st., K.1.

9th Row.—K.2. * K.2, K.2 tog., y.fwd., K.1, y.fwd., sl.1, K.1, p.s.s.o., K.3, rept. from * to last st., K.1.

11th Row.—K.2. * K.1, K.2 tog., y.fwd., K.3, y.fwd., sl.1, K.1, p.s.s.o., K.2, rept. from * to last st., K.1.

13th Row.—K.2. * (K.2 tog., y.fwd) twice, K.1, (y.fwd., sl.1, K.1, p.s.s.o.) twice, K.1, rept. from * to last st., K.1.

15th Row.—K.1, (K.2 tog., y.fwd.) twice, * K.3, y.fwd., sl.1, K.1, p.s.s.o., y.fwd., sl.1, K.2 tog., p.s.s.o., y.fwd., K.2 tog., y.fwd., rept. from * to last 8 sts., K.3, (y.fwd., sl.1, K.1, p.s.s.o.) twice, K.1.

16th Row.—Purl.

These 16 rows form the pattern.

Continue in pattern until work measures 5 (6) ins. from commencement, finishing on a right side row.

DIVIDE FOR ARMHOLES

Next Row.—P.38 (43), cast off 5 sts., P.77 (87) sts. including st. on needle, cast off 5 sts., P. to end.

Continue on the last set of sts. for left side of back, as follows:-

Keeping the pattern correct, K.2 tog. at armhole edge on the next and every following alt. row until 33 (36) sts. remain, finishing on a right side row.

Slip these sts. onto st. holder.

Rejoin yarn to 77 (87) sts. for Front.

K.2 tog. at each end of the needle on the next and every following alt. row until 67 (73) sts. remain, finishing on a right side row.

Slip these sts. onto a st. holder.

Rejoin yarn to remaining 38 (43) sts. and work right side of back to correspond with left side.

Slip these sts. onto st. holder.

SLEEVES - (Both alike)

Using No. 13 needles, cast on 33 (39) sts.

Knit 13 rows.

18 inch SIZE ONLY

Next Row.—(Inc. Row) - * K.2, inc. in next st., rept. from * to last 3 sts., K.3. - (43 sts.).

20 inch SIZE ONLY

Next Row.—(Inc. Row) - K.2, * K.1, inc. in next st., K.2, inc. in next st., rept. from * to last 2 sts., K.2. - (53 sts.).

Change to No. 11 needles.

Continue in pattern as given for Skirt.

Working all inc. sts. in st.st. inc 1 st. at each end of the needle on the 7th and every following 8th row until 49 (59) sts. are on the needle.

Continue without further inc. until work measures 5 (6) ins. from commencement, finishing on a wrong side row.

SHAPE TOP

Keeping the pattern correct, cast off 3 sts. at beg. of the next 2 rows.

18 inch SIZE ONLY

K.2 tog. at each end of the needle on the 5th and following 4th row. - (39 sts.).

Slip these sts. onto st. holder.

20 inch SIZE ONLY

K.2 tog. at each end of the needle on the 3rd and every following 3rd row until 45 sts. remain.

Work 1 row.

Slip these sts. onto st. holder.

YOKE

Slip all sts. onto No. 11 needles as follows:-

33 (36) sts. of left side of back, 39 (45) sts. of sleeve, 67 (73) sts. of Front, 39 (45) sts. of sleeve and 33 (36) sts. of right side of back. (211, 235 sts.).

Rejoin yarn. Purl to end.

1st Row.—(Right Side) - * K.2 tog., rept. from * to last st., K.1. (106, 118 sts.).

Knit 5 rows.

Commencing with a K. row, work 6 rows in st.st. (1 row plain, 1 row purl).

13th Row.—* K.2, K.2 tog., rept. from * to last 2 sts., K.2. (80, 89 sts.).

Knit 5 rows.

Work 6 rows in st.st.

25th Row.—*K.1, K.2 tog., K.1, rept. from * to last 0 (1) st., K.0 (1). (60, 67 sts.).

Change to No. 13 needles.

Knit 4 rows. Cast off.

LEFT BACK BAND

Using No. 13 needles, cast on 6 sts.

Continue in g.st. (every row knit) until band is long enough, when slightly stretched, to fit up left back to neck edge. Cast off.

Pin band into position, mark positions for buttons, the first one $1\frac{1}{4}$ ($1\frac{1}{2}$) ins. from lower edge, the last one $\frac{1}{4}$ inch from neck edge and 3 more equally spaced between.

RIGHT BACK BAND

Work exactly as instructions given for left band working buttonholes to correspond with positions marked for buttons as follows:-

Buttonhole Row.—K.2, cast off 2, K. to end.

Next Row.—K.2, cast on 2 sts., K. to end.

TIGHTS

RIGHT LEG

Using No. 13 needles, cast on 81 (89) sts.

1st Row.—K.1, * P.1, K.1, rept. from * to end.

2nd Row.—P.1, * K.1, P.1, rept. from * to end. Rept. these 2 rows for $1\frac{1}{2}$ ins.

Change to No. 11 needles.

SHAPE BACK

Next Row.—Rib 8, turn.

Next Row.—Sl.1, rib to end.

Next Row.—Rib 16, turn.

Next Row.—Sl.1, rib to end.

Next Row.—Rib 24, turn.

Next Row.—Sl.1, rib to end.

Continue in this manner until the row rib 40, turn has been worked.

Next Row.—Sl.1, rib to end.

Continue in rib over all sts. inc. 1 st. at beg. of the next and every following 6th row until 90 (98) sts. are on the needle.

Continue without further inc. until short edge measures $7\frac{3}{4}$ ($8\frac{3}{4}$) ins., finishing on a wrong side row.

Inc. 1 st. at each end of the needle on the next 3 rows.

Next Row.—Cast on 3 sts., rib to end. — (99, 107 sts.).

SHAPE LEG

K.2 tog. at each end of the needle on the 3rd and every following 3rd row until 45 (49) sts. remain.

Continue without further dec. until leg measures $8\frac{1}{2}$ (9) ins. from crutch, finishing on a wrong side row.

SHAPE INSTEP

Next Row.—Rib 30 (33) sts., turn, rib 15 (17) sts., turn.

Work 2 ($2\frac{1}{4}$) ins. in rib on these 15 (17) sts., finishing on a wrong side row.

Break off yarn.

Rejoin yarn, pick up and K.14 (16) sts. up side of instep, rib 15 (17) sts. of instep, pick up and K.14 (16) sts. down side of instep, rib across 15 (16) sts. from other needle.

Work 7 (9) rows in rib across all sts.

SHAPE SOLE

1st Row.—K.1, sl.1, K.1, p.s.s.o., rib 26 (29), sl.1, K.1, p.s.s.o., rib 11 (13) sts., K.2 tog., rib 26 (29), K.2 tog., K.1.

2nd and Alt. Rows.—Rib to end.

3rd Row.—K.1, sl.1, K.1, p.s.s.o., rib 25 (28) sts., sl.1, K.1, p.s.s.o., rib 9 (11), K.2 tog., rib 25 (28), K.2 tog., K.1.

5th Row.—K.1, sl.1, K.1, p.s.s.o., rib 24 (27), sl.1, K.1, p.s.s.o., rib 7 (9), K.2 tog., rib 24 (27), K.2 tog., K.1.

Continue dec. in this manner until 53 (57) sts. remain.

Cast off in rib.

LEFT LEG.—Work exactly as instructions given for right leg, reversing all shapings.

PRESSING

It is **important** to follow these instructions when making up the garment.

PETER PAN COURTELLE.—Work over the right side

of each piece of the garment with a cool iron.

Taking a small area at a time stretch your knitting lengthways and sideways (pull hard), let it relax, then pat over with the iron, using no pressure.

This evens out the knitting and sets it.

PETER PAN BRI NYLON.—With wrong side of work facing, pin out all pieces to measurements given. Using a warm iron and dry cloth press carefully.

PETER PAN TRICEL NYLON.—With wrong side of work facing, pin out all pieces to measurements given. Using a warm iron and damp cloth press carefully.

MAKING UP

ANGEL TOP

Join sleeve and underarm seams by back stitching, omitting g.st., join g.st. by top sewing. Pin bands into position, sew on by top sewing. Sew on buttons to correspond with buttonholes. Button-hole stitch buttonholes.

TIGHTS

Join front, back and leg seams by back stitching. Join foot seams by top sewing. Fold $\frac{3}{4}$ inch ribbing onto wrong side at waist, and slip stitch to form hem. Thread elastic through hem and join ends.

Press all seams lightly.

A FINAL WORD

You have taken a lot of care in knitting this Peter Pan Design. Your garment deserves equal care when washing. By following these instructions, you will find that the life, shape and softness of your garment will be preserved.

(1) **NEVER USE HOT WATER.**

(2) **Washing.** Place your garment in a well-dissolved solution of **Soap Flakes** and **WARM WATER**. Work the garment gently with the hands for approximately two minutes. **NEVER RUB** the garment and do **NOT** leave it to soak.

(3) **Rinsing.** **EVERY TRACE OF SOAP MUST BE REMOVED.** Rinse in three changes of clean, warm water, squeezing gently, but **NEVER wring** the garment.

(4) **Removing Water.** Place the garment between dry towels and squeeze without twisting.

(5) **Drying.** Immediately spread the garment out to its original shape and size and **DRY FLAT** on a clean towel, **SLOWLY**, and in a warm place. **NEVER** hang up your garment to dry.

WASHING



SO EASY TO WASH AND CARE FOR

Treat your own make of knitteds in Courtelles just as you would bought ones. That is, **WASH** by hand, as soon as they get slightly dirty. Use soapless detergent or soap flakes or powder dissolved in water comfortably hot to the hand. **RINSE** thoroughly. Squeeze lightly or roll in towel. Do **NOT** put through wringer. **DRY** flat.

DO NOT PRESS WITH A DAMP CLOTH, instead, work over the right side of each garment piece with a **COOL** iron (set at Rayon temperature). Taking a small area at a time, stretch your knitting lengthways and sideways (pull hard), let it relax, then pat over it with the iron, using no pressure. This evens out the knitting and sets it.

Our Knitting Bureau will gladly give you any assistance or advice on
Wendy Designs if you write to

CARTER & PARKER LTD., GUISELEY, YORKS.

Prices apply only in Great Britain and Northern Ireland.