

Peter Pan



P484
Darling Chunky



56-66cm.(22-26ins.)

a **Wendy** design

GIRL'S HOODED JACKET

in Peter Pan Darling Chunky

No. P 484
Knitted in Darling
Shades 800 Pure White
801 Pink
802 Blue

Instructions given for 56 cm. (22 inch) Chest, larger sizes given in brackets.
Where only one figure is given this applies to all sizes.

MATERIALS AND MEASUREMENTS

To Fit Chest Sizes.									56 22		61 24		66 26		cm. ins.	
Actual Measurements.									63.5 25		68.5 27		73.5 29		cm. ins.	
Peter Pan Darling Chunky. (40g.)									7		8		8		Balls.	
Lengths of Contrast yarn for embroidery.																
2-6 mm. and 2-7 mm. Milward Knitting Needles. 6 Buttons.																
Length from Back of Neck.									30.5 12		34.5 13½		37 14½		cm. ins.	
Sleeve Seam (with cuff turned back).									19 7½		21.5 8½		23 9		cm. ins.	
NEEDLE SIZES																
Metric	9	7½	7	6½	6	5½	5	4½	4	3¾	3¼	3	2¾	mm.		
English	00	1	2	3	4	5	6	7	8	9	10	11	12			
American	13	11	10½	10	9	8	7	6	5	4	3	2	1			

The quantities of yarn stated are based on average requirements and are therefore approximate.

ABBREVIATIONS

K.-Knit; st(s).-stitch(es); g.st.-garter stitch; tog.-together; rept.-repeat; sl.-slip; inc.-increase; dec.-decrease; t.b.l.-through back of loop; beg.-beginning; alt.-alternate; m.1-make one, pick up loop before next st. and K. it t.b.l.; y.fwd.-yarn forward; cm.-centimetres; ins.-inches.

IMPORTANT

Use **ONLY** the Wendy or Peter Pan yarn specified. (We cannot accept responsibility for an imperfect garment if any other brand is used). Follow our instructions exactly. We advise **every knitter** to check their tension carefully before commencing the garment. All measurements in this design are based on the stated tension

therefore it is essential that the correct tension be obtained and maintained throughout the garment to achieve success.

We recommend the needle size as the size we have used to obtain the tension **but** as each knitter knits differently it may be necessary for some knitters to change their needle size accordingly.

Check your tension carefully

If there are too many stitches to the inch then your tension is tight and you will need to change your needle to a larger size. If there are too few stitches to the inch then your tension is loose and you will need to change your needle to a smaller size.

Keep measuring your knitting throughout to ensure that you are

maintaining correct tension and therefore correct measurements.

TENSION

14 sts. and 26 rows to 10 cm. (4 ins.) over g.st. on 7 mm. Needles.

BACK

Using 6 mm. Needles, cast on 44 (48, 52) sts.

Work 6 rows in g.st. (every row knit, first row is right side).

Change to 7 mm. Needles.

Continue in g.st. until work measures 29 (33, 35.5) cm. 11½ (13, 14) ins. from commencement finishing on a wrong side row.

Shape Shoulders

Cast off 4 (5, 5) sts. at beg. of next 2 rows, then 5 sts. at beg. of following 2 rows, then 5 (5, 6) sts. at beg. of next 2 rows.

Cast off remaining 16 (18, 20) sts.

LEFT FRONT

Using 6 mm. Needles, cast on 28 (30, 32) sts.

Work 6 rows in g.st.

Change to 7 mm. Needles.

Next Row: K. to last 8 sts., sl. these 8 sts. onto a safety pin, turn. 20 (22, 24) sts.

****** Continue in g.st. until work measures 25.5 (29, 31) cm. 10 (11½, 12¼) ins. from commencement finishing at Front edge.

Shape Neck

Cast off 2 sts. at beg. of next row.

Dec. 1 st. at neck edge on every row until 14 (15, 16) sts. remain.

Continue without further dec. until work measures same as Back to Shoulders finishing at side edge.

Shape Shoulder

Cast off 4 (5, 5) sts. at beg. of next row, then 5 sts. at beg. of following alt. row.

Work 1 row.

Cast off remaining 5 (5, 6) sts. ******

RIGHT FRONT

Using 4 mm. Needles, cast on 28 (30, 32) sts.

Work 4 rows in g.st.

Next Row (Buttonhole Row): K.3, y.fwd., K.2tog., K. to end.

Next Row: K. to last 8 sts., sl. these 8 sts. onto a safety pin, turn. 20 (22, 24) sts.

Change to 7 mm. Needles.

Work as instructions given for Left Front from ****** to ******.

SLEEVES (Both Alike)

Using 6 mm. Needles, cast on 30 (32, 34) sts.

Work 8 rows in g.st.

Change to 7 mm. Needles.

Continue in g.st. until Sleeve measures 23 (25.5, 26.5) cm. 9 (10, 10½) ins. from commencement finishing on a right side row.

Cast off.

HOOD

Using 7 mm. Needles, cast on 33 (35, 37) sts.

Continue in g.st.

Work 8 rows.

Next Row: K.30 (32, 34), m.1, K.3.

Work 11 (13, 13) rows.

Next Row: K.31 (33, 35), m.1, K.3.

Work 11 (13, 13) rows.

Next Row: K.32 (34, 36), m.1, K.3.

Work 35 rows.

Next Row: K.31 (33, 35), K.2tog., K.3.

Work 11 (13, 13) rows.

Next Row: K.30 (32, 34), K.2tog., K.3.

Work 11 (13, 13) rows.

Next Row: K.29 (31, 33), K.2tog., K.3.

Work 8 rows.

Cast off.

PRESSING

With wrong side facing, pin out all pieces to measurements given. Press as instructions.

MAKING UP

Join shoulder seams by backstitching.

Left Front Band

With right side facing, sl. sts. from safety pin onto a 6 mm. Needle. Continue in g.st. until band is long enough when slightly stretched to fit up left front to shape neck finishing on a right side row.

Cast off.

Mark positions for buttons on left front band, the first one to correspond with buttonhole already worked, the last one 1 cm. ($\frac{1}{2}$ inch) from cast off edge and 4 more equally spaced between.

Right Front Band

Work as instructions given for left front band working buttonholes as before to correspond with positions marked for buttons.

Pin front bands into position, sew on by top sewing.

Mark depth of armholes 11.5 (12, 13.5) cm. $4\frac{1}{2}$ ($4\frac{3}{4}$, $5\frac{1}{4}$) ins. from shoulder seams.

Join side and sleeve seams by backstitching omitting welt and cuffs, join welt and cuffs by top sewing.

Pin sleeves into position. Sew in by backstitching.

Join back seam of hood by backstitching. Pin hood to neck, folding 4 cm. ($1\frac{1}{2}$ ins.) of front edge of hood onto right side. Place fold to centre of front bands. Sew on by top sewing.

Sew on buttons.

Using Contrast yarns, work flowers in lazy daisy stitch and french knots as illustrated.

Press seams.

WASHING AND PRESSING INSTRUCTIONS

	Washing	Pressing
PETER PAN DARLING	 Warm water, hand or machine wash, short spin, do not wring, dry flat.	 Use a dry cloth and cool iron.



Our Knitting Bureau will gladly give you any assistance or advice on Wendy designs if queries are accompanied by a Wendy or Peter Pan ball band and a stamped addressed envelope

CARTER & PARKER LTD., GUISELEY, YORKS.

© CARTER & PARKER LTD.

Prices apply only in Great Britain and Northern Ireland

Printed in England