

Peter Pan

Double Knit

P628
Price Code C



Wendy

41-61cm. (16-24ins.)

GIRL'S CARDIGAN

in Peter Pan D.K.

No. P.628
Knitted in Spot Print D.K.
Shade 984 Fairy Lights

Instructions given for 41 cm. (16 inch) Chest, larger sizes given in round brackets. Where only one figure is given this applies to all sizes.

MATERIALS AND MEASUREMENTS

To Fit Chest Sizes	41 16	46 18	51 20	56 22	61 24	cm. ins.
Actual Measurements	46.5 18¼	51.5 20¼	56.5 22¼	61.5 24¼	66.5 26¼	cm. ins.
Peter Pan D.K. or Peter Pan Spot Print D.K. (50g.) Peter Pan Mischief D.K. (50g.)	2 2	3 3	3 3	4 4	4 4	Balls Balls
2 — 3¼ mm. (U.K. 10 — U.S.A. 4) and 2 — 4 mm. (U.K. 8 — U.S.A. 6) Milward Knitting Needles. Stitch Holders. 4 Buttons.						
Length from Back of Neck	24 9½	26.5 10½	29 11½	34.5 13½	39.5 15½	cm. ins.
Sleeve Seam	15 6	17.5 7	20.5 8	24 9½	28 11	cm. ins.

IMPORTANT

Use only the Peter Pan yarn specified. We cannot accept responsibility for an imperfect garment if any other brand is used. It is essential to work to the tension stated.

The quantities of yarn stated are based on average requirements and are therefore approximate.

ABBREVIATIONS

K. — Knit; P. — Purl; st(s). — stitch(es); inc. — increase; dec. — decrease; rept. — repeat; tog. — together; alt. — alternate; sl. — slip; sl.1 — slip one; y.fwd. — yarn forward; p.s.s.o. — pass slipped stitch over; m.1 — make one, pick up loop before next st. and K. it through back of loop; O — No stitches or rows to be worked in that particular size; patt. — pattern; cm. — centimetres; ins. — inches.

TENSION

It is important to check

your tension before commencing the garment.

24 sts. and 32 rows to 10 cm. (4 ins.) over patt. on 4 mm. Needles.

If there are too many stitches to 10 cm., then your tension is tight and you will need to change your needle to a larger size. If there are too few stitches to 10 cm., then your tension is loose and you will need to change your needle to a smaller size.

LEFT FRONT

Using 3¼ mm. Needles, cast on 39 (43, 45, 49, 51) sts.

1st Row — K.1, * P.1, K.1, rept. from * to end.

2nd Row — P.1, * K.1, P.1, rept. from * to end.

Rept. the last 2 rows 8 times more, then the 1st Row once.

41 (51, 61) cm. 16 (20, 24) inch sizes only

Next Row (Inc. Row) — Rib 21,

sl. these 21 sts. onto a st. holder, rib 1, m.1, rib to last st., m.1, rib 1. 20 (26, 32) sts.

(46, 56) cm. (18, 22) inch sizes only

Next Row (Inc. Row) — Rib 21, sl. these 21 sts. onto a st. holder, rib 1, m.1, rib to end. (23, 29) sts.

All Sizes

Change to 4 mm. Needles.

Shape Front and Commence Patt.

1st Row (Right Side) — K.1, [K.2tog., y.fwd., K.1] 6 (7, 8, 9, 10) times, K.1.

2nd and Alt Rows — Purl.

3rd Row — K. to last 2 sts., dec. 1 st.

5th Row — K.1, [y.fwd., sl.1, K.1, p.s.s.o., K.1] 6 (7, 8, 9, 10) times.

6th Row — Purl.

7th Row — Knit.

8th Row — Purl.

** Continue in patt. as set, dec. 1 st. at Front edge on the 5th (5th, 3rd, 5th, 5th) and every following 10 (10, 8, 10, 10)th row until 17 (19, 20, 25, 28) sts., then on every following 12 (12, 10, 12, 12)th row until 15 (17, 18, 21, 23) sts. remain.

Continue without further shaping until Front measures 24 (26.5, 29, 34.5, 39.5) cm. 9½ (10½, 11½, 13½, 15½) ins. from commencement finishing on a wrong side row.

Shape Shoulder

Cast off remaining 15 (17, 18, 21, 23) sts. **

RIGHT FRONT

Using 3¼ mm. Needles, cast on 39 (43, 45, 49, 51) sts.

Work 4 rows in rib as given for Left Front

Next Row (Buttonhole Row) — Rib 3, y.fwd., K.2tog., rib 12, y.fwd., K.2tog., rib to end.

Work a further 14 rows in rib working a buttonhole as before on the 12th row.

41 (51, 61) cm. 16 (20, 24) inch sizes only

Next Row (Inc. Row) — Rib 1, m.1, rib to last 22 sts., m.1, rib 1, turn, sl. remaining 21 sts. onto a st. holder. 20 (26, 32) sts.

(46, 56) cm. (18, 22) inch sizes only

Next Row (Inc. Row) — Rib to last 22 sts., m.1, rib 1, turn, sl. remaining 21 sts. onto a st. holder. (23, 29) sts.

All Sizes

Change to 4 mm. Needles.

Shape Front and Commence Patt.

1st Row (Right Side) — K.2, [K.2tog., y.fwd., K.1] 6 (7, 8, 9, 10) times.

2nd and Alt. Rows — Purl.

3rd Row — Dec. 1 st., K. to end.

5th Row — K.1, [y.fwd., sl.1, K.1, p.s.s.o., K.1] 6 (7, 8, 9, 10) times.

6th Row — Purl.

7th Row — Knit.

8th Row — Purl.

Work from ** to ** as given for Left Front.

BACK

Using 3¼ mm. Needles, cast on 53 (59, 65, 71, 77) sts.

Work 20 rows in rib as given for Left Front, inc. 1 st. at each end of the needle on the last row. 55 (61, 67, 73, 79) sts. Change to 4 mm. Needles.

Commence Patt.

1st Row (Right Side) — K.1, * K.2tog., y.fwd., K.1, rept. from * to end.

2nd and Alt Rows — Purl.

3rd Row — Knit.

5th Row — K.1, * y.fwd., sl.1, K.1, p.s.s.o., K.1, rept. from * to end.

7th Row — Knit.

8th Row — Purl.

These 8 rows form the patt.

Continue in patt. until Back is 9 rows less than Left Front to shoulder finishing on a right side row.

Shape Back Neck

Keeping patt. correct.

Next Row — Patt. 23 (25, 26, 29, 31), cast off centre 9 (11, 15, 15, 17) sts., patt. to end.

Continue on the last set of sts. as follows:-

Dec. 1 st. at neck edge on the next 8 rows.

Shape Shoulder

Cast off remaining 15 (17, 18, 21, 23) sts.

With right side facing, rejoin yarn to remaining sts. at neck edge.

Work as instructions given for other side.

Mark centre st. of back neck with a coloured thread.

SLEEVES (Both Alike)

Using 3¼ mm. Needles, cast on 31 (33, 35, 37, 39) sts.

Work 4 cm. (1½ ins.) in rib as given for Left Front finishing

on a 2nd Row, inc. 1 st. at each end of the needle on the last row. 33 (35, 37, 39, 41) sts. Change to 4 mm. Needles.

Commence Patt.

1st Row (Right Side) — K.2 (0, 1, 2, 0), * K.2tog., y.fwd., K.1, rept. from * to last 1 (2, 0, 1, 2) sts., K.1 (2, 0, 1, 2).

2nd and Alt Rows — Purl.

3rd Row — Inc. in first st., K. to last st., inc. in last st.

5th Row — K.3 (1, 2, 3, 1), * y.fwd., sl.1, K.1, p.s.s.o., K.1, rept. from * to last 2 (0, 1, 2, 0) sts., K.2 (0, 1, 2, 0).

6th Row — Purl.

Keeping 8 row patt. correct and working all inc. sts. into patt., inc. 1 st. at each end of the needle on every following 6 (6, 4, 4, 4)th row from previous inc. until 43 (49, 45, 53, 55) sts. are on the needle.

(56, 61) cm. (22, 24) inch sizes only

Inc. 1 st. at each end of the needle on every following 6th row until (61, 67) sts. are on the needle.

All Sizes

Continue without further inc. until Sleeve measures 15 (17.5, 20.5, 24, 28) cm. 6 (7, 8, 9½, 11) ins. from commencement finishing on a wrong side row. Cast off loosely.

PRESSING

With wrong side facing, pin out all pieces to measurements given. Press as instructions.

MAKING UP

Join shoulder seams by back-stitching.

Left Front Band

With right side facing, using 3¼ mm. Needles, rejoin yarn to 21 sts. on st. holder.

Continue in rib until band is long enough when slightly stretched to fit up left front and across back neck to marker finishing on a 2nd Row.

Cast off in rib.

Right Front Band

With **wrong** side facing, using

3¼ mm. Needles, rejoin yarn to 21 sts. on st. holder.

Continue in rib until band is long enough when slightly stretched to fit up right front and across back neck to marker finishing on a 2nd Row.

Cast off in rib.

Join seam at back neck by top sewing.

Pin front bands into position, sew on by top sewing.

Mark depth of armholes 9 (10, 11.5, 12.5, 14) cm. 3½ (4, 4½, 5, 5½) ins. from shoulder seams.

Join side seams to markers and sleeve seams by backstitching omitting rib, join rib by top sewing.

Pin sleeves into position, sew in by backstitching.

Sew on buttons.

Press seams.

WASHING AND PRESSING INSTRUCTIONS

Peter Pan	Washing  Warm water, hand or machine wash, short spin, do not wring, dry flat.	Pressing  Use a dry cloth and cool iron.
-----------	---	---

Our Knitting Bureau will gladly give you any assistance or advice on Wendy designs if queries are accompanied by a Wendy or Peter Pan ball band and a stamped addressed envelope.

CARTER & PARKER LTD., GUISELEY, YORKS.