

Peter Pan

double KNIT

P754
PRICE CODE C

36-51cm. (14-20ins.)

see reverse
for alternative design



Easy Knit

Wendy

GARTER STITCH LAYETTE in Peter Pan D.K.

Instructions given for 36 cm. (14 inch) Chest, larger sizes given in round brackets.
Where only one figure is given, this applies to all sizes.

MATERIALS AND MEASUREMENTS

The photograph shows the 41 cm. garments.

To Fit Chest Sizes.	36 14	41 16	46 18	51 20	cm. ins.
JACKET AND SWEATER Actual Measurements.	41 16	46 18	51 20	56 22	cm. ins.
JACKET Peter Pan D.K., Spot Print D.K. or Mischief D.K. (50g.)	2	2	3	3	Balls
SWEATER Peter Pan D.K., Spot Print D.K. or Mischief D.K. (50g.)	2	2	2	2	Balls
TROUSERS Peter Pan D.K., Spot Print D.K. or Mischief D.K. (50g.)	3	3	4	4	Balls
MITTENS Peter Pan D.K., Spot Print D.K. or Mischief D.K. (50g.)	1	1	1	1	Ball
SCARF Peter Pan D.K., Spot Print D.K., or Mischief D.K. (50g.)	1				Ball
BLANKET Peter Pan D.K., Spot Print D.K. or 1st Contrast Mischief D.K. (50g.) 2nd Contrast 3rd Contrast	1 1 1				Ball Ball Ball
2 - 3¼ mm. (U.K. 10 - U.S.A. 4) and 2 - 4 mm. (U.K. 8 - U.S.A. 6) Wendy Knitting Needles. 5 Buttons for Jacket. 3 Buttons for Sweater. 2 cm. (½ inch) Elastic for Trousers. 68 cm. (27 ins.) of narrow Ribbon for Mittens. Stitch Holders.					
JACKET AND SWEATER Length from Back of Neck.	19 7½	21 8¼	23 9	25.5 10	cm. ins.
Sleeve Seam.	15 6	17 6¾	19 7½	21 8¼	cm. ins.
TROUSERS Length to waist (including Leg Cuff).	33.5 13¾	34 13½	37 14½	39 15½	cm. ins.
BLANKET	45.5 x 61 18 x 24				cm. ins.

Please note that the limitations of the printing process mean that the actual colour will not always precisely match the colours in the photograph.

IMPORTANT

Use only the Peter Pan yarn specified. We cannot accept responsibility for an imperfect garment if any other brand is used. It is essential to work to the

tension stated.

The quantities of yarn stated are based on average requirements and are therefore approximate.

EASY
KNIT

No. P754
Knitted in Shades
Peter Pan D.K. 302 Peach Cream
Mischief D.K. 65 Honeybun
Spot Print D.K. 768 Lullaby

ABBREVIATIONS

A. — 1st Contrast; **alt.** — alternate; **B.** — 2nd Contrast; **C.** — 3rd Contrast; **cm.** — centimetres; **dec.** — decrease; **g.st.** — garter stitch (every row knit); **inc.** — increase; **ins.** — inches; **K.** — Knit; **rept.** — repeat; **st(s).** — stitch(es); **tog.** — together; **y.fwd.** — yarn forward.

TENSION

It is important to check your tension before commencing the garment.

22 sts. and 40 rows to 10 cm. (4 ins.) over g.st. on 4 mm. Needles.

If there are too many stitches to 10 cm., then your tension is tight and you will need to change your needle to a larger size. If there are too few stitches to 10 cm., then your tension is loose and you will need to change your needle to a smaller size.

JACKET

BACK

****** Using 3¼ mm. Needles, cast on 44(50, 56, 62) sts. Work 5 rows in g.st. Change to 4 mm. Needles. Continue in g.st. (first row is Right Side) until work measures 19(21, 23, 25.5) cm. 7½(8¼, 9, 10) ins. from commencement finishing on a wrong side row. ******

Shape Shoulders

Cast off.

Left Front

Using 3¼ mm. Needles, cast on 25(28, 31, 34) sts. Work 5 rows in g.st. Change to 4 mm. Needles. Continue in g.st. (first row is Right Side) until work measures 16(18, 20, 22) cm. 6¼(7, 7¾, 8¾) ins. from commencement finishing on a right side row.

(Work 1 row more for Right Front).

Shape Neck

Next Row — Cast off 7(8, 9, 10) sts., K. to end.

Dec. 1 st. at neck edge on every following alt. row until 14(16, 18, 20) sts. remain.

Continue without further shaping until Front measures same as Back to shoulders finishing on a wrong side row.

Shape Shoulder

Cast off.

Mark positions for buttons on Left Front, the first one 7 rows from lower edge, the last one 4 rows below neck shaping and 3 more equally spaced between.

RIGHT FRONT

Work as instructions given for Left Front **at the same time** working buttonholes to correspond with positions marked for buttons as follows:-

Buttonhole Row — K.3, y.fwd., K.2 tog., K. to end.

SLEEVES (Both Alike)

Using 3¼ mm. Needles,

cast on 30(30, 32, 32) sts. Work 5 rows in g.st. Change to 4 mm. Needles. Continue in g.st., (first row is Right Side) inc. 1 st. at each end of the needle on the next and every following 8th row until 42(44, 48, 50) sts. are on the needle.

Continue without further inc. until Sleeve measures 17(19, 21, 23) cm. 6¾(7½, 8¼, 9) ins. from commencement finishing on a wrong side row. Cast off.

HOOD

Using 3¼ mm. Needles, cast on 42(46, 50, 54) sts. Work 4 rows in g.st.

Next Row (Inc. Row) — K.3(1, 3, 3), * inc. in next st., K.1, rept. from * to last 5(3, 5, 5) sts., inc. in next st., K.4(2, 4, 4). 60(68, 72, 78) sts.

Change to 4 mm. Needles. Continue in g.st. (first row is Right Side) until work measures 15(17, 20, 22) cm., 6(6¾, 8, 8¾) ins. from commencement finishing on a wrong side row. Cast off.

SWEATER

BACK

Work as instructions given for Back of Jacket from ** to **.

Next Row — Cast off 30(34, 38, 42) sts., K. to end.

Work 4 rows in g.st. for button band across remaining 14(16, 18, 20) sts. Cast off.

FRONT

Work as instructions given

for Back of Jacket until Front measures 16(18, 20, 22) cm. 6¼(7, 7¾, 8¾) ins. from commencement finishing on a wrong side row.

Shape Neck

Next Row — K.18(20, 22, 24), cast off next 8(10, 12, 14) sts., K. to end. Continue on the last 18(20, 22, 24) sts. as follows:-

*** Dec. 1 st. at neck edge on the next and every following alt. row until 14(16, 18, 20) sts. remain. Continue without further shaping until Front measures 19(21, 23, 25.5) cm. 7½(8¼, 9, 10) ins. from commencement finishing on a wrong side row. ***

Shape Shoulder

Cast off.

With **wrong** side facing, rejoin yarn to remaining 18(20, 22, 24) sts. at neck edge.

Work as instructions given for other side from *** to ***.

Next Row (Buttonhole Row) — K.2(2, 4, 4) sts., [K.2 tog., y.fwd., K.4(5, 5, 6)] twice, K.2 tog., y.fwd., K.2.

Work 3 rows in g.st. Cast off.

SLEEVES (Both Alike)

Work exactly as instructions given for Sleeves of Jacket.

TROUSERS

(Work 2 pieces alike).

Using 3¼ mm. Needles, cast on 36(40, 44, 48) sts. Work 24 rows in g.st.

Next Row (Inc. Row) —

K.1(3, 2, 1), * inc. in next st., K.2., rept. from * to last 2(4, 3, 2) sts., inc. in next st., K.1(3, 2, 1). 48(52, 58, 64) sts.

Change to 4 mm. Needles. Continue in g.st. (first row is Right Side), inc. 1 st. at each end of the needle on the next and every following alt. row until 68(78, 84, 90) sts. are on the needle.

Mark each end of last row. Continue in g.st. until work measures 30.5(32.5, 34.5, 37) cm. 12¼(12½, 13½, 14½) ins. from commencement finishing on a wrong side row. Change to 3¼ mm. Needles. Work 10 rows more in g.st. Cast off.

MITTENS (Both Alike)

Using 3¼ mm. Needles, cast on 26(28, 28, 30) sts. Work 5 rows in g.st. Change to 4 mm. Needles. Continue in g.st. (first row is Right Side) until work measures 5(6.5, 6.5, 7.5) cm. 2(2½, 2½, 3) ins. from commencement finishing on a wrong side row.

Shape Top

1st Row — * K.2 tog., K.9(10, 10, 11), K.2 tog., rept. from * once more. 22(24, 24, 26) sts.

2nd Row — Knit.

3rd Row — * K.2 tog., K.7(8, 8, 9), K.2 tog., rept. from * once more. 18(20, 20, 22) sts.

4th Row — Knit.

5th Row — * K.2 tog., K.5(6, 6, 7), K.2 tog., rept. from * once more. 14(16, 16, 18) sts.

Cast off.

SCARF

Using 4 mm. Needles, cast on 33 sts.

Work in g.st. (first row is Right Side) until work measures 70 cm. (27½ ins.) from commencement finishing on a wrong side row.

Cast off.

BLANKET

First Section

Using 4mm. Needles and A., cast on 33 sts.

Work 60 rows in g.st.

Break off A., join in B.

Work 60 rows in g.st.

Break off B., join in A.

Work 60 rows in g.st.

Break off A., join in C.

Work 60 rows in g.st.

Cast off.

Second Section

Using 4 mm. Needles and C., cast on 33 sts.

Work 60 rows in g.st.

Break off C., join in A.

Work 60 rows in g.st.

Break off A., join in C.

Work 60 rows in g.st.

Break off C., join in B.

Work 60 rows in g.st.

Cast off.

Third Section

Using 4 mm. Needles and B., cast on 33 sts.

Work 60 rows in g.st.

Break off B., join in C.

Work 60 rows in g.st.

Break off C., join in B.

Work 60 rows in g.st.

Break off B., join in A.

Work 60 rows in g.st.

Cast off.

PRESSING

With wrong side facing, pin

out all pieces to measurements given. Press as instructions given on ball band.

MAKING UP JACKET

Join shoulder seams by top sewing.

Fold cast off edge of hood in half and join top seam by top sewing.

Fold front edge of hood onto right side for 3 cm. (1¼ ins.) and sew down edges.

Placing centre of cast on edge of hood to centre of back neck and side edges 3 sts. from each front edge, sew hood in position evenly round neck edge by top sewing.

SWEATER

Join right shoulder seam by top sewing.

Place buttonhole band over button band, sl.st. together at side edge.

JACKET AND SWEATER

Mark depth of armholes 9.5(10, 11, 11.5) cm.

3¾(4, 4¼, 4½) ins. from shoulder seams.

Join side seams to markers and sleeve seams by top sewing, reversing seams for cuff.

Pin sleeves into position, sew in by top sewing.

Turn back cuffs.

Sew on buttons.

TROUSERS

Join leg seams to markers by top sewing. Join front and back seams by top sewing, reversing seams for cuff.

Join elastic into a ring and

place inside waistband.
Work a herringbone casing
stitch over elastic onto
every alt. st. to enclose the
elastic.
Fold leg cuff onto right
side.

MITTENS

Join side seams by top
sewing, reversing seam for
turnback.
Sew one end of ribbon to
each mitten.

BLANKET

Join sections together by
top sewing.
Using A., work crossed
stitching along each seam.
Press seams.



KNITTING NOTES

TENSION: It is really important
that you spend a little time before
beginning to knit trying out the
tension given in the pattern.
There are 2 main reasons for
this:

Before we begin to write the
patterns for you we have to work
out what the tension is, so we
know how many sts to tell you to
cast on so we know how wide the
garment should be.

If you do not get the same tension
as we do, your garment will not be
the same size, also you may need
more yarn than we have said. It is
much easier in the long run to find
out if your tension is not the same
at the very start than half way
through and you waste yarn.

M.1 (Make 1) This is the invisible
way of increasing. Pick up the
loop that is between the stitch you
have just worked and the next
stitch on the left hand needle, put
it on the needle and knit into the
back of it — see diagram.



K.2 tog. (Knit 2 together) is a
basic way of decreasing a stitch or
decreasing to the right. Insert the
right hand needle into the 2nd
stitch on left hand needle and into
the first st, wind the yarn round
the needle, pull the loop through
and take both stitches off the
needle together.

Inc (increase) Into the next stitch
knit it the usual way, then without
taking the stitch off, knit into the
back of it.

y.fwd. (yarn forward) this is the
way of making a hole between 2
knit stitches. The yarn is already
at the back of the work, bring it to
the front under the right hand
needle, then to knit the next stitch,
take the yarn over the top of the
needle.

MAKING UP THE KNITTING

Top sewing: Used for side
seams, front bands, sleeve seams.
With right sides of both pieces
facing, secure yarn at lower edge.
Pick up 1 stitch from other side
and pull it through. Take the
needle across to other side and
pick up next stitch and pull yarn
through. Take needle back to first
side and pull through. Continue in
this way, pulling stitches up as
you go until the seam is
complete.



© Carter & Parker Ltd.

Our Knitting Bureau will gladly give you any assistance or advice on Wendy designs if queries are accompanied by a
Wendy or Peter Pan ball band and a stamped addressed envelope.

CARTER & PARKER LTD., GUISELEY, YORKS.

Prices apply only in Great Britain and Northern Ireland
Printed in England

Peter Pan

double KNIT

P754
PRICE CODE C

36-51cm. (14-20ins.)

see reverse
for alternative design



Easy Knit

Gwendy