

Wendy

JAZZ

£1.85P

4940

PRICE CODE C

Height 25 cm. (9¾ ins.)



SNOWMAN in Wendy Jazz

MATERIALS AND MEASUREMENTS

Actual Height, to top of Hat	25 9 ³ / ₄	cm. ins.
SNOWMAN		
Wendy Jazz (50g.)	2	Balls
Wendy Courtelle D.K. (25g.)		
Blue	1	Ball
Red	1	Ball
White	1	Ball
2 - 4 mm. (U.K. 8 - U.S.A. 6) Wendy Knitting Needles. Washable Toy Filling. Oddments of D.K. yarn in Black for buttons and eyes and Orange for nose. For Crochet Hat: 3.50 mm. (U.K. 9 - U.S.A. E4) Crochet Hook.		

Please note that the limitations of the printing process mean the actual colour will not always precisely match the colours in the photograph.

IMPORTANT

Use only the Wendy yarn specified. We cannot accept responsibility for an imperfect garment if any other brand is used. It is essential to work to the tension stated. The quantities of yarn stated are based on average requirements and are therefore approximate.

ABBREVIATIONS

K. - Knit; **P.** - Purl; **st(s).** - stitch(es); **g.st.** - garter stitch (every row knit); **st.st.** - stocking stitch (1 row knit, 1 row purl); **rept.** - repeat; **tog.** - together; **d.c.** - double crochet; **ch.** - chain; **s.s.** - slip stitch; **cm.** - centimetres; **ins.** - inches.

TENSION

It is important to check your tension before commencing the garment.

Snowman: 32 sts. and 40 rows to 10 cm. (4 ins.) over g.st. on 4 mm. Needles.

Scarf and Knitted Hat: 24 sts. and 32 rows to 10 cm. (4 ins.) over st.st. on 4 mm. Needles.

If there are too many stitches to 10 cm., then your tension is tight and you will need to change your needle to a larger size. If there are too few stitches to 10 cm., then your tension is loose and you will need to change your needle to a smaller size.

SNOWMAN

LOWER BODY

Using 4 mm. Needles and Jazz, cast on 35 sts.

Work in g.st. until work measures 25 cm. (9³/₄ ins.), finishing on a wrong side row. Cast off.

UPPER BODY

Using 4 mm. Needles and Jazz, cast on 30 sts.

Work in g.st. until work measures 20 cm. (7³/₄ ins.), finishing on a wrong side row. Cast off.

HEAD

Using 4 mm. Needles and Jazz, cast on 20 sts.

Work in g.st. until work measures 15 cm. (6 ins.), finishing on a wrong side row. Cast off.

ARMS (Make 2)

Using 4 mm. Needles and Jazz, cast on 17 sts.

Work in g.st. until work measures 10 cm. (4 ins.), finishing on a wrong side row. Cast off.

MAKING UP

Join cast-on and cast-off edges of Lower Body to form a tube. Run gathering thread around one row end edge and pull up tightly to close edge completely. Fasten off securely. Run gathering thread around other row end edge and pull up slightly. Insert toy filling so Lower Body is firmly filled. Pull up gathering thread so that edge is completely closed and fasten off securely.

In same way, make and fill Upper Body, Head and Arm pieces. Place Upper Body onto Lower Body and stitch in place. Place Head onto Upper Body and stitch in place. Position Arms on Upper Body as in photograph and stitch in place.

Using Black D.K. yarn and photograph as a guide, embroider french knot buttons down front of Upper and Lower Body and eyes on Head.

Nose

Using 4 mm. Needles and Orange D.K., cast on 5 sts.

Work in g.st. for 6 rows, finishing on a wrong side row.

Break yarn and thread through all 5 sts. Pull up tight and fasten off securely. Sew row end edges together to form a carrot shape, leaving cast-on edge open. Using photograph as a guide, sew cast-on edge to Head.

SCARF

Using 4 mm. Needles and Red D.K., cast on 14 sts.

Knit 2 rows, finishing on a wrong side row. Join in White D.K.

Next Row (Right side) - Using White, knit.

Next Row - Using White, K.2, P.10, K.2.

Next Row - Using Red, knit.

Next Row - Using Red, K.2, P.10, K.2.

Rept. last 4 rows until Scarf measures 57 cm.

4940

Knitted in Wendy Jazz

Shades: 1290 Dixieland

Knitted in Wendy Courtelle DK

Shades: 86 Royal

84 Cherry Red

70 White

(22¹/₂ ins.), finishing on a right side row and after 1 row using Red.

Break off White.

Using Red, cast off knitwise (on wrong side).

CROCHET HAT

Using 3.50 mm. Crochet Hook and Blue D.K., make 3 ch. and join with a s.s. to form a ring.

1st Round (Right side) - 1 ch. (does NOT count as st.), 8 d.c. into ring, s.s. to first d.c. 8 sts.

2nd Round - 1 ch. (does NOT count as st.), 2 d.c. into each d.c. to end, s.s. to first d.c. 16 sts.

3rd Round - 1 ch. (does NOT count as st.), [2 d.c. into next d.c., 1 d.c. into next d.c.] 8 times, s.s. to first d.c. 24 sts.

4th Round - 1 ch. (does NOT count as st.), [2 d.c. into next d.c., 1 d.c. into each of next 2 d.c.] 8 times, s.s. to first d.c. 32 sts.

5th Round - 1 ch. (does NOT count as st.), 1 d.c. into each d.c. to end, s.s. to first d.c.

6th Round - 1 ch. (does NOT count as st.), **working into back loops only of sts. of previous round**, 1 d.c. into each d.c. to end, s.s. to first d.c.

7th, 8th and 9th Rounds - As 5th Round. Join in Red D.K.

10th and 11th Rounds - As 5th Round **but using Red**.

Break off Red and complete Hat using Blue **only**.

12th Round - As 5th Round.

13th Round - 1 ch. (does NOT count as st.), 2 d.c. into each d.c. to end, s.s. to first d.c. 64 sts.

14th and 15th Rounds - As 5th Round. Fasten off.

KNITTED HAT

Using 4 mm. Needles and Blue D.K., cast on 82 sts.

Working in g.st., continue as follows:-

Work 2 rows, finishing on a wrong side row.

3rd Row (Right side) - [K.7, K.2tog.] 9 times, K.1. 73 sts.

Work 1 row.

5th Row - [K.6, K.2tog.] 9 times, K.1. 64 sts.

Work 1 row.

7th Row - [K.5, K.2tog.] 9 times, K.1. 55 sts.

Work 1 row.

9th Row - [K.4, K.2tog.] 9 times, K.1. 46 sts.

Work 1 row.

Commencing with a K. row, now working in st.st. throughout, continue as follows:-

Join in Red D.K.

Work 2 rows.

Break off Red and continue using Blue **only**.

Work 6 rows, finishing on a wrong side row.

Next Row (Right side) - Purl.

Shape Crown

1st and Every Following Alt. Row (Wrong side) - Purl.

2nd Row - [K.3, K.2tog.] 9 times, K.1. 37 sts.

4th Row - [K.2, K.2tog.] 9 times, K.1. 28 sts.

6th Row - [K.1, K.2tog.] 9 times, K.1. 19 sts.

8th Row - [K.2tog.] 9 times, K.1. 10 sts.

9th Row - Purl.

Break yarn and thread through remaining 10 sts. Pull up tight and fasten off securely. Join back seam.

Our Knitting Bureau will gladly give any assistance or advice on Wendy designs if queries are accompanied by a Wendy or Peter Pan ball band and a stamped addressed envelope.

CARTER & PARKER LTD., GUISELEY, YORKS.

A Member of the Thomas Ramsden Group

