

8398

Emu

DK

DOUBLE
KNITTING

■

QK

QUICKERKNIT

MACHINE
WASHABLE
BABY WOOL
QUICKERKNIT

TWO SIZES
19-20 inch



7½p

ANGEL TOP

with BONNET
and TIGHTS



The garments featured on the front cover were knitted in Emu Machine Washable Baby Wool, Shade No. 714, New White and Shade No. 226, New Pink.

DK

EMU SCOTCH DOUBLE KNITTING
EMU DOUBLE KNITTING CROCHET WOOL
EMU DOUBLE CREPE
EMU BRI-NYLON DOUBLE KNITTING
EMU SUPERLITE BRI-NYLON DOUBLE KNITTING

QK

EMU COURTELLE BABY QUICKERKNIT
EMU BRI-NYLON BABY QUICKERKNIT
EMU SUPERLITE BRI-NYLON BABY QUICKERKNIT
EMU MACHINE WASHABLE BABY WOOL QUICKERKNIT

TENSION

We recommend that you test your tension before commencing the garment. A tension square to measure 4" x 4" should be knitted and, before this sample is measured, it should be pinned out and pressed according to the special instructions given under the heading TO MAKE UP.

ANGEL TOP

To fit Chest	ins.	19	20
MACHINE WASHABLE BABY WOOL Main Colour	25 grm. balls	4	4
Contrast Colour	25 grm. balls	3	3
DOUBLE KNITTING Main Colour	balls	4	4
Contrast Colour	balls	3	3
QUICKERKNIT Main Colour	balls	4	4
Contrast Colour	balls	2	2
Length	ins.	8½	9½
Sleeve seam to Eyelet Holes	ins.	5	6
DOUBLE KNITTING and MACHINE WASHABLE BABY WOOL One pair of short and one pair of long Aero Knitting Needles size 8. 6 Buttons. ¾ yard of Ribbon.			
QUICKERKNIT One pair of short and one pair of long Aero Knitting Needles size 7. 6 Buttons. ¾ yard of Ribbon.			
TENSION 5½ stitches and 8 rows to 1 square inch measured over stocking stitch.			

ABBREVIATIONS

K., knit; p., purl; st(s), stitch(es); st.st., stocking stitch; rep., repeat; inc., increase(ing); dec., decrease(ing); tog., together; sl., slip; p.s.o., pass slipped stitch over; y.f., yarn forward; m1, make one by picking up the bar that lies between st. just worked and next st. on left-hand needle and knitting into the back of it; y.o.n., yarn over needle; y.r.n., yarn round needle; m.c., main colour; c.c., contrast colour.

TO OBTAIN A PERFECT RESULT YOU MUST USE ONE OF THE EMU QUALITIES RECOMMENDED ON THIS LEAFLET. EMU WOOLS WILL NOT ACCEPT ANY RESPONSIBILITY FOR THE FINISHED GARMENT UNLESS ONE OF THESE QUALITIES IS USED.

NOTE—These instructions are written in two sizes, stitches and measurements for the smaller size being given in the ordinary way, the largest size being bracketed in the following space.

MACHINE WASHABLE BABY WOOL

FRONT

Using size 8 needles and m.c., cast on 88 (99) sts. and k.3 rows. Commence pattern.

1st row: (Right side) K.

2nd row: P.

3rd row: * [P.2 tog.] twice, [m.1 (see abbreviations), k.1] 3 times, m.1, [p.2 tog.] twice, rep. from * to end.

4th row: P.

Change to c.c. and work rows 1 to 4.

Change to m.c. and work rows 1 to 4.

Rep. these 12 pattern rows 2 (3) times more.

1st size only

Work rows 1 to 4 inclusive.

Both sizes

Mark each end of last row with a coloured thread.

Keeping continuity of pattern, work a further 8 (12) rows. Leave these sts. on a spare needle.

RIGHT SIDE OF BACK

Using size 8 needles and m.c., cast on 49 (60) sts. and k.2 rows.

Next row: K.5 and slip them onto a safety pin, k. to end. 44 (55) sts.

Now work the 12 pattern rows as given for Front 3 (4) times in all. 36 (48) rows of pattern.

1st size only

Work rows 1 to 4 inclusive.

Both sizes

Mark side edge of last row with a coloured thread.

Keeping continuity of pattern, work a further 8 (12) rows. Leave these sts. on a spare needle.

LEFT SIDE OF BACK

Using size 8 needles and m.c., cast on 49 (60) sts. and k.2 rows.

Next row: K. to last 5 sts., then slip these 5 sts. onto a safety pin. 44 (55) sts. Complete to match Right Side of Back.

SLEEVES

Using size 8 needles and m.c., cast on 44 sts. and k.3 rows. Now work rows 1 to 4 of pattern, Change to c.c.

Next row: K.

Next row: P.

Next row: (Make Eyelet Holes) K.3, * y.f., k.2 tog., rep. from * to last st., k.1.

Next row: P.

Change to m.c. and work rows 1 to 4.

Now work the 12 pattern rows, as given on Front, 3 (4) times.

1st size only

Work rows 1 to 4 inclusive.

Both sizes

Mark each end of last row with a coloured thread.

Keeping continuity of pattern, work a further 8 (12) rows. Leave these sts. on a spare needle.

BUTTONHOLE BAND

Using size 8 needles and m.c., slip the 5 sts. on safety pin on Right Side of Back onto needle. With right side

Do write if in need of advice on this leaflet to JANET MINTON, E

Copyright printed in England

of work facing, join in yarn at inside edge. Work in garter st. (every row k.). Work 4 (10) rows.

Buttonhole row: K.1, k.2 tog., y.f., k.2. Make 3 more buttonholes with 11 rows between each. Work a further 9 rows. Leave these sts. on a safety pin.

BUTTON BAND

Using size 8 needles and m.c., slip the 5 sts. on safety pin on Left Side of Back onto needle. With wrong side of work facing, join in yarn at inside edge. Work to match Buttonhole Band, omitting buttonholes.

YOKE

Using the long size 8 needles and m.c., work across all sts. as follows:

1st size only

Commencing at Left Side of Back, k. across the 5 sts. on Button Band, [k.2 tog.] 16 times, k.12 across Left Side of Back, k. across the 44 sts. of first Sleeve, [k.2 tog.] 44 times across Front, k. across the 44 sts. on second Sleeve, k.12, [k.2 tog.] 16 times across Right Side of Back, then k. across the 5 sts. on Buttonhole Band. (198 sts.)

2nd size only

Commencing at Left Side of Back, k. across the 5 sts. on Button Band, [k.2 tog.] 27 times, k.1 across Left Side of Back, k. across the 44 sts. of first Sleeve, k.2, [k.2 tog.] 47 times, k.3 across Front, k. across the 44 sts. on second Sleeve, k.1, [k.2 tog.] 27 times across Right Side of Back, then k. across the 5 sts. on Buttonhole Band. (206 sts.)

Both sizes

Next row: K.5, p. to last 5 sts., k.5.

Buttonhole row: K. to last 4 sts., k.2 tog., y.f., k.2.

Next row: K.5, p. to last 5 sts., k.5.

Commence shaping.

Next row: K.

Next row: K.5, p. to last 5 sts., k.5.

Rep. the last 2 rows once more.

Next row: K.13 (17), * sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.7, rep. from * to last 17 (21) sts., sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.12 (16). 168 (176) sts.

Next row: K.5, p. to last 5 sts., k.5.

Next row: K.

Next row: K.5, p. to last 5 sts., k.5.

Next row: K.12 (16), * sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.5, rep. from * to last 16 (20) sts., sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.11 (15). 138 (146) sts.

Next row: K.5, p. to last 5 sts., k.5.

Buttonhole row: K. to last 4 sts., k.2 tog., y.f., k.2.

Next row: K.5, p. to last 5 sts., k.5.

Next row: K.11 (15), * sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.3, rep. from * to last 15 (19) sts., sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.10 (14). 108 (116) sts.

Next row: K.5, p. to last 5 sts., k.5.

Next row: K.10 (14), * sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.1, rep. from * to last 14 (18) sts., sl.1, k.1, p.s.s.o., k.1, k.2 tog., k.9 (13). 78 (86) sts.

Next row: K.5, p. to last 5 sts., k.5.

Next row: K.7 (9), * k.2 tog., k.5 (4), rep. from * to last 8 (11) sts., k.2 tog., k.6 (9). 68 (74) sts.

Change to size 10 needles.

K.1 row.

Next row: K.5, p. to last 5 sts., k.5.

Next row: (Make Eyelet Holes) K.5, p.2 (1), * y.r.n., p.2 tog., p.2, rep. from * to last 9 (8) sts., y.r.n., p.2 tog., p.2 (1), k.5.

Next row: K.5, p. to last 5 sts., k.5.

K.1 row.

Cast off.

DOUBLE KNITTING

Follow instructions for Machine Washable Baby Wool.

QUICKERKNIT

Follow instructions for Machine Washable Baby Wool, but using size 7 needles instead of 8 and size 9 needles instead of 10.

BONNET

To fit size	ins.	19	20
MACHINE WASHABLE BABY WOOL Main Colour	25 grm. balls	1	1
Small amount of contrast colour			
DOUBLE KNITTING Main Colour	balls	1	1
Small amount of contrast colour			
QUICKERKNIT Main colour	balls	1	1
Small amount of contrast colour			
DOUBLE KNITTING and MACHINE WASHABLE BABY WOOL One pair each of Aero Knitting Needles size 8 and 10. Medium size crochet hook. 1 yard of Ribbon.			
QUICKERKNIT One pair each of Aero Knitting Needles size 7 and 9. Medium size crochet hook. 1 yard of Ribbon.			
TENSION 5½ stitches and 8 rows to 1 square inch measured over stocking stitch.			

MACHINE WASHABLE BABY WOOL

Using size 10 needles and m.c., cast on 77 (77) sts. and k.3 rows. Change to size 8 needles. Now work the 12 pattern rows as given on Front of Angel Top 3 times in all. (36 rows of pattern.)

1st size only

Work rows 1 to 4 inclusive.

2nd size only

Work rows 1 to 8 inclusive.

Both sizes

Continue in m.c. only.

Shape Back

1st row: K.3, * sl.1, k.1, p.s.s.o., k.10, k.2 tog., rep. from * 4 times more, k.4. (67 sts.)

2nd and alternate rows: K.

3rd row: K.3, * sl.1, k.1, p.s.s.o., k.8, k.2 tog., rep. from * 4 times more, k.4. (57 sts.)

5th row: K.3, * sl.1, k.1, p.s.s.o., k.6, k.2 tog., rep. from * 4 times more, k.4. (47 sts.)

7th row: K.3, * sl.1, k.1, p.s.s.o., k.4, k.2 tog., rep. from * 4 times more, k.4. (37 sts.)

9th row: K.3, * sl.1, k.1, p.s.s.o., k.2, k.2 tog., rep. from * 4 times more, k.4. (27 sts.)

11th row: K.2 tog. all along row to last st., k.1. (14 sts.)

12th row: K.2 tog. all along row. (7 sts.) Break off yarn, thread through remaining sts., draw up and fasten off securely.

DOUBLE KNITTING

Follow instructions for Machine Washable Baby Wool.

QUICKERKNIT

Follow instructions for Machine Washable Baby Wool, but using size 7 needles instead of 8 and size 9 needles instead of 10.

TIGHTS

To fit size	ins.	19	20
MACHINE WASHABLE BABY WOOL	25 grm. balls	4	4
DOUBLE KNITTING	balls	4	4
QUICKERKNIT	balls	4	4
DOUBLE KNITTING and MACHINE WASHABLE BABY WOOL One pair each of Aero Knitting Needles size 8 and 10. Elastic to fit waist.			
QUICKERKNIT One pair each of Aero Knitting Needles size 7 and 9. Elastic to fit waist.			
TENSION 5½ stitches and 8 rows to 1 square inch measured over stocking stitch.			

RIGHT LEG

★ Using size 10 needles, cast on 54 (56) sts. and work 4 rows in k.1, p.1 rib.

Next row: Rib 2 (4), * y.o.n., k.2 tog., rib 2, rep. from * to end. Work a further 3 rows in rib. Change to size 8 needles. ★

Shape Back

1st row: K.11 (12) sts. and turn.

2nd and alternate rows: P.

3rd row: K.22 (23) sts. and turn.

5th row: K.33 (34) sts. and turn.

7th row: K.44 (45) sts. and turn.

8th row: P.

★ Continue in st.st. (1 row k., 1 row p.) and work across all sts. for 22 (24) rows. Inc. 1 st. at each end of the next and every following 6th row until there are 64 (66) sts. on the needle, then 1 st. at each end of the next 4 rows. 72 (74) sts.

Commence Leg Shaping

Dec. 1 st. at each end of the next and 2 following alternate rows, then 1 st. at each end of every following 3rd row until 32 (32) sts. remain. Work a further ½ in. h., ending with a p. row and dec. 1 st. at each end of last row on 1st size only. 30 (32) sts. ★★

Shape Foot

Next row: K.27 (29) sts. and turn.

Next row: P.8 (8) sts. and turn.

Work in st.st. on these sts. for 2 inches, ending with a p. row. Break off yarn. Rejoin yarn to inside edge of the 19 (21) sts. already knitted, pick up and k.14 sts. along first side of instep, k.8 toe sts., pick up and k.14 sts. along second side of instep, then k. remaining 3 sts. 58 (60) sts.

Next row: P.

K.2 rows. Rep. the last 3 rows once more.

Next row: P.

1st row: K.6 (7), [k.2 tog.] twice, k.25 (26), [k.2 tog.] twice, k.19 (19). 54 (56) sts.

2nd and every alternate row: P.

3rd row: K.5 (6), [k.2 tog.] twice, k.23 (24), [k.2 tog.] twice, k.18 (18). 50 (52) sts.

5th row: K.4 (5), [k.2 tog.] twice, k.21 (22), [k.2 tog.] twice, k.17 (17). 46 (48) sts.

7th row: K.3 (4), [k.2 tog.] twice, k.19 (20), [k.2 tog.] twice, k.16 (16). 42 (44) sts. Cast off.

LEFT LEG

Follow instruction for Right Leg from ★ to ★.

K.1 row.

Shape Back

1st row: P.11 (12) sts. and turn.

2nd and alternate rows: K.

3rd row: P.22 (23) sts. and turn.

5th row: P.33 (34) sts. and turn.

7th row: P.44 (45) sts. and turn.

8th row: K.

Next row: P. across all sts.

Follow instructions for Right Leg from ★★ to ★★.

Shape Foot

Next row: K.11 (11) sts. and turn.

Next row: P. 8 (8) sts. and turn.

Work in st.st. on these sts. for 2 inches, ending with a p. row. Break off yarn. Rejoin yarn to inside edge of the 3 sts. already knitted, pick up and k.14 sts. along first side of instep, k.8 toe sts., pick up and k.14 sts. along second side of instep, then k. remaining 19 (21) sts. 58 (60) sts.

Next row: P.

K.2 rows. Rep. the last 3 rows once more.

Next row: P.

1st row: K.19 (19), [k.2 tog.] twice, k.25 (26), [k.2 tog.] twice, k.6 (7). 54 (56) sts.

2nd and every alternate row: P.

3rd row: K.18 (18), [k.2 tog.] twice, k.23 (24), [k.2 tog.] twice, k.5 (6). 50 (52) sts.

5th row: K.17 (17), [k.2 tog.] twice, k.21 (22), [k.2 tog.] twice, k.4 (5). 46 (48) sts.

7th row: K.16 (16), [k.2 tog.] twice, k.19 (20), [k.2 tog.] twice, k.3 (4). 42 (44) sts. Cast off.

DOUBLE KNITTING

Follow instructions for Machine Washable Baby Wool.

QUICKERKNIT

Follow instructions for Machine Washable Baby Wool, but using size 7 needles instead of 8 and size 9 needles instead of size 10.

TO MAKE UP

SPECIAL PRESSING INSTRUCTIONS

BABY QUICKERKNIT COURTELLE—DO NOT PRESS

BRI-NYLON

BABY QUICKERKNIT BRI-NYLON

Pin out to correct measurements and press with a cool iron over a dry cloth, omitting ribbing.

WOOL

Pin out to correct measurements and press with a warm iron over a damp cloth, omitting ribbing.

MACHINE WASHABLE BABY WOOL

Pin out and press as given for Wool. It is essential that the seams are joined with the same yarn as used for the making as other yarns could shrink and spoil the shape of the garment. Make sure that all seams are fastened off securely as the agitation of a washing machine could loosen these stitches. Sew all buttons on securely.

ANGEL TOP

Using back stitch, join side and sleeve seams as far as coloured and. Join remaining section of sleeve to remaining section of armhole. Sew on buttons. Thread ribbon through eyelet holes at neck, bringing ends out to tie.

BONNET

Join seam from centre of crown for 2½ inches. Using m.c., work a row of double crochet along neck edge. Sew ribbon to each side.

TIGHTS

Using a back stitch, join back, front, leg and foot seams. Thread elastic through eyelet holes at waist.

