

REWARD
DOUBLE
KNITTING

51-71 cm
20-28 inch



as featured on TV

Garment knitted in shades White, Silver Smoke, Black, Harebell, Chocolate, Natural, Buttercup and Scarlet.

Photographed at The Bluebell Railway, Sussex.

To fit Chest					
cm	51	56	61	66	71
in.	20	22	24	26	28
Garment measurement					
cm	56	61	66	71	76
in.	22	24	26	28	30
Length					
cm	32	37	39	42	44
in.	12½	14½	15½	16½	17½
Sleeve seam					
cm	19	22	24	30	36
in.	7½	8½	9½	12	14

Amount required

Balls					
(White)	3	3	3	4	4

You will also need small amounts of Silver Smoke, Black, Harebell, Chocolate, Natural, Buttercup and Scarlet.

Milward knitting needles size 3¼ mm (10 U.K.) and 4 mm (8 U.K.).

Tension

11 sts. and 15 rows to 5 cm (approximately 2 in.) measured over st.st.

Check your tension and use finer needles if you have less stitches to the inch or thicker needles if you have more stitches to the inch.

Abbreviations

K., knit; **p.**, purl; **st(s)**, stitch(es); **st.st.**, stocking stitch (1 row k., 1 row p.); **beg.**, beginning; **inc.**, increase(ing); **dec.**, decrease(ing); **M.1**, Make one worked thus; pick up the bar between stitch just worked and next stitch on left-hand needle and knit into the back of it; **mm**, millimetres; **cm**, centimetres; **in.**, inch(es).

Note: Instructions for the larger sizes are given in () brackets; where one figure only is given, this applies to all sizes.

ROBIN Wools cannot accept the responsibility for the completed garment if any yarn other than the ROBIN quality stated is used.

ROBIN Wools Ltd., Milford House, 6-10 Kirby Street, London EC1N 8TS.

BACK

Using 3¼ mm needles and White, cast on 60 (66, 72, 78, 82) sts.

Work 1½ (1½, 2, 2, 2) in. k.1, p.1 rib.

Change to 4 mm needles.

Proceed in st.st. until back measures 12½ (14½, 15½, 16½, 17½) in. from cast-on edge, ending p. row.

To Shape Shoulders

Cast off 10 (11, 12, 13, 14) sts. at beg. of next 2 rows and 9 (10, 11, 12, 13) sts. at beg. of following 2 rows.

Cut off yarn and leave remaining 22 (24, 26, 28, 28) sts. on a holder.

FRONT

Using 3¼ mm needles and White, cast on 60 (66, 72, 78, 82) sts.

Work 1½ (1½, 2, 2, 2) in. k.1, p.1 rib.

Change to 4 mm needles.

Work 8 rows st.st.

Join on and cut off colours as required.

Use separate small balls of yarn for each area of colour and twist yarns together at back of work when changing colour to avoid making a hole.

Reading odd numbered (k.) rows from right to left and even numbered (p.) rows from left to right work in patt. from Chart, or if preferred the front of the sweater can be knitted in st.st. throughout and the motif Swiss Darned onto the garment – see end of instructions.

Beg. row 1, work the 54 patt. rows of Chart, then continue in White only until front measures 10½ (12½, 13, 13½, 14½) in. from cast-on edge, ending p. row.

To Shape Neck

Next row: K.22 (24, 27, 29, 31), turn and leave remaining sts. on a spare needle.

Work on first set of sts. as follows:

Dec. 1 st. at neck edge on every row until 19 (21, 23, 25, 27) sts. remain.

Work straight until front measures same as back up to beg. of shoulder shaping, ending at side edge.

To Shape Shoulder

Cast off 10 (11, 12, 13, 14) sts. at beg. of next row. Work 1 row. Cast off.

Return to sts. on spare needle. With right side facing, slip first 16 (18, 18, 20, 20) sts. onto a holder, join White to next st. and k. to end of row: 22 (24, 27, 29, 31) sts.

Now complete to match first side of neck.

SLEEVES


Using 3¼ mm needles and White, cast on 34 (36, 38, 38, 40) sts.

Work 1½ (1½, 2, 2, 2) in. k.1, p.1 rib.

Inc. row: Rib 8 (7, 8, 8, 8), * M.1, rib 6 (7, 7, 7, 8), rep. from * to last 8 (8, 9, 9, 8) sts., M.1, rib to end: 38 (40, 42, 42, 44) sts.

Change to 4 mm needles.

71-77.



Key

□	white
◻	grey
■	black
◼	blue
▤	brown
✕	red
◻	yellow
◻	beige

Proceed in st.st. but inc. 1 st. each end of 3rd and every following 4th (4th, 4th, 4th, 5th) row until there are 56 (60, 66, 72, 78) sts.

Work straight until sleeve measures $7\frac{1}{2}$ ($8\frac{1}{2}$, $9\frac{1}{2}$, 12, 14) in. from cast-on edge ending p. row.

(Length can be adjusted here).

To Shape Top

Cast off 11 (12, 13, 14, 15) sts. at beg. of next 4 rows.

Cast off.

NECKBAND

Join right shoulder seam. With right side facing, join White to neck at left front shoulder and using a $3\frac{1}{4}$ mm needle, pick up and k.13 (13, 14, 15, 15) sts.

down left side of front neck, k. the front neck sts. from holder, pick up and k.13 (13, 14, 15, 15) sts. up right side of front neck, then k. the back neck sts. from holder but inc. 1 st. at each end: 66 (70, 74, 80, 80) sts.

Work 1 in. k.1, p.1 rib.

Cast off loosely in rib.

TO MAKE UP

See ball band for pressing and washing details. Join left shoulder and neckband seam. Place markers 5 ($5\frac{1}{2}$, 6, $6\frac{1}{2}$, 7) in. below shoulders on back and front to denote beg. of armholes.

Set in sleeves between markers, then join side and sleeve seams.


Using red and yellow, em-

broider lines on Engine as in picture.

SWISS DARNING

The principle of Swiss Darning is that the embroidered stitch follows the line of the knitted stitch.

First draw the needle through the two threads at the base of the stitch to be covered, then insert the needle again behind the two threads at the top of the same stitch, draw the needle through, thus covering one side of the knitted stitch. Now insert the needle again through the base of the same stitch and the second side of the stocking stitch loop on the front of the fabric will be covered.




U.K.	000	00	0	1	2	3	4	5	6	7	8	9	10	11	12	13	14
AMERICAN	15	13	12	11	$10\frac{1}{2}$	10	9	8	7	6	5	4	3	2	1	0	00
mm METRIC	10	9	8	$7\frac{1}{2}$	7	$6\frac{1}{2}$	6	$5\frac{1}{2}$	5	$4\frac{1}{2}$	4	$3\frac{3}{4}$	$3\frac{1}{4}$	3	$2\frac{3}{4}$	$2\frac{1}{4}$	2

COURTELLE



Copyright printed in Great Britain



R.1.

13632
H&T