

Crochet Purse Pattern – Camera





CROCHET PURSE PATTERN- CAMERA

****Gauge:** 6 sc = 2 cm

****Hook Size:** 2 mm

****Yarn:** All the yarn used in this pattern is 4 Ply 100% Acrylic Yarn (diameter about: 1.5 mm)

****Color:** No color-coding are given due to the differences of color in different location, always choose the closest color to the photo given. Always experiment with different colors to create new look.

Since the size does not really matter, you can experiment with different yarn and hook to create different sizes.

Ingredients:

For PURSE:	ZIPPER:
Light grey yarn – 40g	Light grey
Others – Less than 5 g	

Note: The weight of yarn given are estimated figure, might be slightly different for individual due to tension, gauge and type of yarn.

CROCHET PURSE PATTERN – CAMERA

Using light grey yarn, ch 16,

Rnd 1: Sc into the 2nd ch from the hook, sc in next 13 sc, 3 sc in next sc, working on the back of the ch, sc in next 13 sc, 2 sc in next sc, sl st into the first sc. (32)

Rnd 2: Ch 1, 3 sc in next sc, sc in next 13 sc, 3 sc in next sc, sc in next sc, 3 sc in next sc, sc in next 13 sc, 3 sc in next sc, sc in next sc, sl st into the first sc. (40)

Rnd 3: Ch 1, sc in next sc, 3 sc in next sc, sc in next 15 sc, 3 sc in next sc, sc in next 3 sc, 3 sc in next sc, sc in next 15 sc, 3 sc in next sc, sc in next 3 sc, sl st into the first sc. (48)

Rnd 4: Ch 1, sc in next 2 sc, 3 sc in next sc, sc in next 17 sc, 3 sc in next sc, sc in next 5 sc, 3 sc in next sc, sc in next 17 sc, 3 sc in next sc, sc in next 5 sc, sl st into the first sc. (56)

Rnd 5: Ch 1, sc in next 3 sc, 3 sc in next sc, sc in next 19 sc, 3 sc in next sc, sc in next 7 sc, 3 sc in next sc, sc in next 19 sc, 3 sc in next sc, sc in next 7 sc, sl st into the first sc. (64)

Rnd 6: Ch 1, sc in next 4 sc, 3 sc in next sc, sc in next 21 sc, 3 sc in next sc, sc in next 9 sc, 3 sc in next sc, sc in next 21 sc, 3 sc in next sc, sc in next 9 sc, sl st into the first sc. (72)

Rnd 7: Ch 1, sc in next 5 sc, 3 sc in next sc, sc in next 23 sc, 3 sc in next sc, sc in next 11 sc, 3 sc in next sc, sc in next 23 sc, 3 sc in next sc, sc in next 11 sc, sl st into the first sc. (80)

Rnd 8: Ch 1, sc in next 6 sc, 3 sc in next sc, sc in next 25 sc, 3 sc in next sc, sc in next 13 sc, 3 sc in next sc, sc in next 25 sc, 3 sc in next sc, sc in next 13 sc, sl st into the first sc. (88)

Rnd 9: Ch 1, sc in next 7 sc, 3 sc in next sc, sc in next 27 sc, 3 sc in next sc, sc in next 15 sc, 3 sc in next sc, sc in next 27 sc, 3 sc in next sc, sc in next 15 sc, sl st into the first sc. (96)

Rnd 10: Ch 1, sc in next 8 sc, 3 sc in next sc, sc in next 29 sc, 3 sc in next sc, sc in next 17 sc, 3 sc in next sc, sc in next 29 sc, 3 sc in next sc, sc in next 17 sc, sl st into the first sc. (104)

Rnd 11: Ch 1, working on the outer loop, sc in each sc around, sl st into the first sc. (104)

Rnd 12-13: Ch 1, sc in each sc around, sl st into the first sc. (104)

Finish off.

Start again at the 47th st on Rnd 13,

Rnd 14: Ch 1, sc in next 58 sc. (58)

Finish off.

Repeat all the above step to make another piece.

To sew the zipper:

1. Use a zip not shorter than 7 inches long (longer does not matter), sew to the lower / bottom part of the empty Rnd 14. You may use running stitch or any other stitch that you think is suitable.
2. Using brown yarn, join Rnd 14 (front piece) to Rnd 14 (back piece).
3. Lastly, sew the upper part of the zipper to the top part of the purse.

Lens

Using dark grey yarn, ch 4, sl st into the first ch to create a ring,

Rnd 1: Ch 1, 6 sc into the ring, sl st into the first sc. (6)

Rnd 2: Ch 1, 2 sc in each of sc around, sl st into the first sc. (12)

Rnd 3: Ch 1, [2 sc in next sc, sc in next sc] repeat 6 times, sl st into the first sc. (18)

Rnd 4: Ch 1, [2 sc in next sc, sc in next 2 sc] repeat 6 times, sl st into the first sc. (24)

Rnd 5: Ch 1, [2 sc in next sc, sc in next 3 sc] repeat 6 times, sl st into the first sc. (30)

Rnd 6: Ch 1, [2 sc in next sc, sc in next 4 sc] repeat 6 times, sl st into the first sc. (36)

Rnd 7: Ch 1, [2 sc in next sc, sc in next 5 sc] repeat 6 times, sl st into the first sc. (42)

Change to light grey yarn,

Rnd 8: Ch 1, working on the inner loop, sc in each sc around, sl st into the first sc. (42)

Rnd 9: Ch 1, working on the outer loop, [2 sc in next sc, sc in next 6 sc] repeat 6 times, sl st into the first sc. (48)

Rnd 10: Ch 1, working on the outer loop, sc in each sc around, sl st into the first sc. (48)

Finish Off.

Button

Using black yarn, ch 4,

Rnd 1: Sc into the 2nd ch from the hook, sc in next sc, 3 sc in next sc, working on the back of the ch, sc in next sc, 2 sc in next sc, sl st into the first sc. (8)

Finish off. Sew to the left top corner.

Flash

Using white yarn, ch 5,

Rnd 1: Sc into the 2nd ch from the hook, sc in next 2 sc, 3 sc in next sc, working on the back of the ch, sc in next 2 sc, 2 sc in next sc, sl st into the first sc. (10)

Rnd 2: Ch 1, 2 sc in next sc, sc in next 2 sc, [2 sc in next sc] repeat 3 times, sc in next 2 sc, [2 sc in next sc] repeat 2 times, sl st into the first sc. (16)

Finish off. Sew to the right top corner.

Handle

Using light grey yarn, ch 3,

Rnd 1: Sc into the 2nd ch from the hook, sc in next sc. (2)

Rnd 2-54: Ch 1, turn, sc in next 2 sc. (2)

Finish Off. Sew to the side of the purse.

Instructions abbreviations:

Sl st – slip stitch

Sc – single crochet

Dc – double crochet

Hdc – half double crochet

Trb – treble

Ch – chain

----- END -----